
PhotoScan Python Reference

Release 1.3.2

Agisoft LLC

May 11, 2017

CONTENTS

1	Overview	3
2	Application Modules	5
3	Python API Change Log	69
	Python Module Index	81

Copyright (c) 2017 Agisoft LLC.

OVERVIEW

1.1 Introduction to Python scripting in PhotoScan Professional

This API is in development and will be extended in the future PhotoScan releases.

Note: Python scripting is supported only in PhotoScan Professional edition.

PhotoScan Professional uses Python 3.5 as a scripting engine.

Python commands and scripts can be executed in PhotoScan in one of the following ways:

- From PhotoScan “Console” pane using it as standard Python console.
- From the “Tools” menu using “Run script...” command.
- From command line using “-r” argument and passing the path to the script as an argument.

The following PhotoScan functionality can be accessed from Python scripts:

- Open/save/create PhotoScan projects.
- Add/remove chunks, cameras, markers.
- Add/modify camera calibrations, ground control data, assign geographic projections and coordinates.
- Perform processing steps (align photos, build dense cloud, build mesh, texture, decimate model, etc...).
- Export processing results (models, textures, orthophotos, DEMs).
- Access data of generated models, point clouds, images.
- Start and control network processing tasks.

APPLICATION MODULES

PhotoScan module provides access to the core processing functionality, including support for inspection and manipulation with project data.

The main component of the module is a Document class, which represents a PhotoScan project. Multiple Document instances can be created simultaneously if needed. Besides that a currently opened project in the application can be accessed using `PhotoScan.app.document` property.

The following example performs main processing steps on existing project and saves back the results:

```
>>> import PhotoScan
>>> doc = PhotoScan.app.document
>>> doc.open("project.psz")
>>> chunk = doc.chunk
>>> chunk.matchPhotos(accuracy=PhotoScan.HighAccuracy, generic_preselection=True,
↳reference_preselection=False)
>>> chunk.alignCameras()
>>> chunk.buildDenseCloud(quality=PhotoScan.MediumQuality)
>>> chunk.buildModel(surface=PhotoScan.Arbitrary, interpolation=PhotoScan.
↳EnabledInterpolation)
>>> chunk.buildUV(mapping=PhotoScan.GenericMapping)
>>> chunk.buildTexture(blending=PhotoScan.MosaicBlending, size=4096)
>>> doc.save()
```

class `PhotoScan.Accuracy`
Alignment accuracy in [HighestAccuracy, HighAccuracy, MediumAccuracy, LowAccuracy, LowestAccuracy]

class `PhotoScan.Antenna`
GPS antenna position relative to camera.

fixed
Fix antenna flag.

Type `boolean`

location
Antenna coordinates.

Type `Vector`

location_acc
Antenna location accuracy.

Type `Vector`

location_ref
Antenna location reference.

Type `Vector`

rotation

Antenna rotation angles.

Type *Vector*

rotation_acc

Antenna rotation accuracy.

Type *Vector*

rotation_ref

Antenna rotation reference.

Type *Vector*

class PhotoScan.Application

Application class provides access to several global application attributes, such as document currently loaded in the user interface, software version and OpenCL device configuration. It also contains helper routines to prompt the user to input various types of parameters, like displaying a file selection dialog or coordinate system selection dialog among others.

An instance of Application object can be accessed using PhotoScan.app attribute, so there is usually no need to create additional instances in the user code.

The following example prompts the user to select a new coordinate system, applies it to the active chunk and saves the project under the user selected file name:

```
>>> import PhotoScan
>>> doc = PhotoScan.app.document
>>> crs = PhotoScan.app.getCoordinateSystem("Select Coordinate System", doc.chunk.
↳ crs)
>>> doc.chunk.crs = crs
>>> path = PhotoScan.app.getSaveFileName("Save Project As")
>>> try:
...     doc.save(path)
... except RuntimeError:
...     PhotoScan.app.messageBox("Can't save project")
```

class ConsolePane

ConsolePane class provides access to the console pane

clear()

Clear console pane.

contents

Console pane contents.

Type *string*

class Application.PhotosPane

PhotosPane class provides access to the photos pane

resetFilter()

Reset photos pane filter.

setFilter(items)

Set photos pane filter.

Parameters **items** (list of *Camera* or *Marker*) – filter to apply.

class Application.Settings

PySettings()

Application settings

load()

Load settings from disk.

save()

Save settings on disk.

setValue (*key*, *value*)

Set settings value. :arg key: Key. :type key: string :arg value: Value. :type value: object

value (*key*)

Return settings value. :arg key: Key. :type key: string :return: Settings value. :rtype: object

Application.activated

PhotoScan activation status.

Type boolean

Application.addMenuItem (*label*, *func* [, *shortcut*] [, *icon*])

Create a new menu entry.

Parameters

- **label** (*string*) – Menu item label.
- **func** (*function*) – Function to be called.
- **shortcut** (*string*) – Keyboard shortcut.
- **icon** (*string*) – Icon.

Application.addMenuSeparator (*label*)

Add menu separator.

Parameters **label** (*string*) – Menu label.

Application.captureModelView ([*width*] [, *height*] [, *transparent*] [, *hide_items*] [, *source*] [, *mode*])

Capture image from model view.

Parameters

- **width** (*int*) – Image width.
- **height** (*int*) – Image height.
- **transparent** (*boolean*) – Sets transparent background.
- **hide_items** (*boolean*) – Hides all items.
- **source** (*PhotoScan.DataSource*) – Data source. Note: Data-Source.DenseCloudData value is not supported.
- **mode** (*PhotoScan.ModelViewMode*) – Model view mode.

Returns Captured image.

Return type *Image*

Application.captureOrthoView ([*width*] [, *height*] [, *transparent*] [, *hide_items*] [, *source*])

Capture image from ortho view.

Parameters

- **width** (*int*) – Image width.
- **height** (*int*) – Image height.
- **transparent** (*boolean*) – Sets transparent background.

- **hide_items** (*boolean*) – Hides all items.
- **source** (*PhotoScan.DataSource*) – Data source.

Returns Captured image.

Return type *Image*

Application.console

Console pane.

Type *ConsolePane*

Application.cpu_enable

Use CPU when GPU is active.

Type *boolean*

Application.document

Main application document object.

Type *Document*

Application.enumGPUDevices()

Enumerate installed GPU devices.

Returns A list of devices.

Return type *list*

Application.getBool (*label=''*)

Prompt user for the boolean value.

Parameters **label** (*string*) – Optional text label for the dialog.

Returns Boolean value selected by the user.

Return type *bool*

Application.getCoordinateSystem (*[label][, value]*)

Prompt user for coordinate system.

Parameters

- **label** (*string*) – Optional text label for the dialog.
- **value** (*CoordinateSystem*) – Default value.

Returns Selected coordinate system. If the dialog was cancelled, None is returned.

Return type *CoordinateSystem*

Application.getExistingDirectory (*[hint]*)

Prompt user for the existing folder.

Parameters **hint** (*string*) – Optional text label for the dialog.

Returns Path to the folder selected. If the input was cancelled, empty string is returned.

Return type *string*

Application.getFloat (*label='', value=0*)

Prompt user for the floating point value.

Parameters

- **label** (*string*) – Optional text label for the dialog.
- **value** (*float*) – Default value.

Returns Floating point value entered by the user.

Return type float

`Application.getInt (label='', value=0)`

Prompt user for the integer value.

Parameters

- **label** (*string*) – Optional text label for the dialog.
- **value** (*int*) – Default value.

Returns Integer value entered by the user.

Return type int

`Application.getOpenFileName ([hint][, filter])`

Prompt user for the existing file.

Parameters

- **hint** (*string*) – Optional text label for the dialog.
- **filter** (*string*) – Optional file filter, e.g. “Text file (.txt)” or “.txt”. Multiple filters are separated with “;”.

Returns Path to the file selected. If the input was cancelled, empty string is returned.

Return type string

`Application.getOpenFileNames ([hint][, filter])`

Prompt user for one or more existing files.

Parameters

- **hint** (*string*) – Optional text label for the dialog.
- **filter** (*string*) – Optional file filter, e.g. “Text file (.txt)” or “.txt”. Multiple filters are separated with “;”.

Returns List of file paths selected by the user. If the input was cancelled, empty list is returned.

Return type list

`Application.getSaveFileName ([hint][, filter])`

Prompt user for the file. The file does not have to exist.

Parameters

- **hint** (*string*) – Optional text label for the dialog.
- **filter** (*string*) – Optional file filter, e.g. “Text file (.txt)” or “.txt”. Multiple filters are separated with “;”.

Returns Path to the file selected. If the input was cancelled, empty string is returned.

Return type string

`Application.getString (label='', value='')`

Prompt user for the string value.

Parameters

- **label** (*string*) – Optional text label for the dialog.
- **value** (*string*) – Default value.

Returns String entered by the user.

Return type string

`Application.gpu_mask`

GPU device bit mask: 1 - use device, 0 - do not use (i.e. value 5 enables device number 0 and 2).

Type int

`Application.messageBox(message)`

Display message box to the user.

Parameters `message` (*string*) – Text message to be displayed.

`Application.photos_pane`

Photos pane.

Type PhotosPane

`Application.quit()`

Exit application.

`Application.settings`

Application settings.

Type Settings

`Application.update()`

Update user interface during long operations.

`Application.version`

PhotoScan version.

Type string

`Application.viewpoint`

Viewpoint in the model view.

Type *Viewpoint*

class `PhotoScan.BlendingMode`

Blending mode in [AverageBlending, MosaicBlending, MinBlending, MaxBlending, DisabledBlending]

class `PhotoScan.Calibration`

Calibration object contains camera calibration information including image size, focal length, principal point coordinates and distortion coefficients.

b1

Affinity.

Type float

b2

Non-orthogonality.

Type float

cx

Principal point X coordinate.

Type float

cy

Principal point Y coordinate.

Type float

error (*point*, *proj*)

Returns projection error.

Parameters

- **point** (*Vector*) – Coordinates of the point to be projected.
- **proj** (*Vector*) – Pixel coordinates of the point.

Returns 2D projection error.

Return type *Vector*

f

Focal length.

Type float

height

Image height.

Type int

k1

Radial distortion coefficient K1.

Type float

k2

Radial distortion coefficient K2.

Type float

k3

Radial distortion coefficient K3.

Type float

k4

Radial distortion coefficient K4.

Type float

load (*path*, *format*='xml')

Loads calibration from file.

Parameters

- **path** (*string*) – path to calibration file
- **format** (*string*) – Calibration format in ['xml', 'australis', 'photomodeler', 'calibcam', 'calcam', 'inpho', 'usgs'].

Returns success of operation

Return type boolean

p1

Tangential distortion coefficient P1.

Type float

p2

Tangential distortion coefficient P2.

Type float

p3

Tangential distortion coefficient P3.

Type float**p4**

Tangential distortion coefficient P4.

Type float**project** (*point*)

Returns projected pixel coordinates of the point.

Parameters **point** (*Vector*) – Coordinates of the point to be projected.**Returns** 2D projected point coordinates.**Return type** *Vector***save** (*path*, *format*=*'xml'*, [*pixel_size*], [*label*])

Saves calibration to file.

Parameters

- **path** (*string*) – path to calibration file
- **format** (*string*) – Calibration format in ['xml', 'australis', 'photomodeler', 'calibcam', 'calcam', 'inpho', 'usgs'].
- **pixel_size** (*Vector*) – Pixel size in mm used to convert normalized calibration coefficients to Australis and CalibCam coefficients.
- **label** (*string*) – Calibration label used in Australis, CalibCam and CalCam formats.

Returns success of operation**Return type** boolean**type**

Camera model.

Type *Sensor.Type***unproject** (*point*)

Returns direction corresponding to the image point.

Parameters **point** (*Vector*) – Pixel coordinates of the point.**Returns** 3D vector in the camera coordinate system.**Return type** *Vector***width**

Image width.

Type int**class** PhotoScan.**Camera**

Camera instance

```
>>> import PhotoScan
>>> chunk = PhotoScan.app.document.addChunk()
>>> chunk.addPhotos(["IMG_0001.jpg", "IMG_0002.jpg"])
>>> camera = chunk.cameras[0]
>>> camera.photo.meta["Exif/FocalLength"]
'18'
```


The following example describes how to create multispectral camera layout:

```
>>> import PhotoScan
>>> doc = PhotoScan.app.document
>>> chunk = doc.chunk
>>> rgb = ["RGB_0001.JPG", "RGB_0002.JPG", "RGB_0003.JPG"]
>>> nir = ["NIR_0001.JPG", "NIR_0002.JPG", "NIR_0003.JPG"]
>>> images = [[rgb[0], nir[0]], [rgb[1], nir[1]], [rgb[2], nir[2]]]
>>> chunk.addPhotos(images, PhotoScan.MultiplaneLayout)
```

class Reference

CameraReference object contains measured camera location data.

accuracy

Camera location accuracy.

Type *Vector*

accuracy_ypr

Camera rotation accuracy.

Type *Vector*

enabled

Enabled flag.

Type *boolean*

location

Camera coordinates.

Type *Vector*

rotation

Camera rotation angles.

Type *Vector*

Camera.center

Camera station coordinates for the photo in the chunk coordinate system.

Type *Vector*

Camera.enabled

Enables/disables the photo.

Type *boolean*

Camera.error (point, proj)

Returns projection error.

Parameters

- **point** (*Vector*) – Coordinates of the point to be projected.
- **proj** (*Vector*) – Pixel coordinates of the point.

Returns 2D projection error.

Return type *Vector*

Camera.frames

Camera frames.

Type list of *Camera*

Camera.group

Camera group.

Type *CameraGroup*

Camera.key
Camera identifier.

Type *int*

Camera.label
Camera label.

Type *string*

Camera.mask
Camera mask.

Type *Mask*

Camera.meta
Camera meta data.

Type *MetaData*

Camera.open (*path*[, *layer*])
Loads specified image file.

Parameters

- **path** (*string*) – Path to the image file to be loaded.
- **layer** (*int*) – Optional layer index in case of multipage files.

Camera.orientation
Image orientation (1 - normal, 6 - 90 degree, 3 - 180 degree, 8 - 270 degree).

Type *int*

Camera.photo
Camera photo.

Type *Photo*

Camera.planes
Camera planes.

Type list of *Camera*

Camera.project (*point*)
Returns coordinates of the point projection on the photo.

Parameters **point** (*Vector*) – Coordinates of the point to be projected.

Returns 2D point coordinates.

Return type *Vector*

Camera.reference
Camera reference data.

Type *CameraReference*

Camera.selected
Selects/deselects the photo.

Type *boolean*

Camera.sensor
Camera sensor.

Type *Sensor*

`Camera.shutter`
Camera shutter.

Type *Shutter*

`Camera.thumbnail`
Camera thumbnail.

Type *Thumbnail*

`Camera.transform`
4x4 matrix describing photo location in the chunk coordinate system.

Type *Matrix*

`Camera.unproject (point)`
Returns coordinates of the point which will have specified projected coordinates.

Parameters `point` (*Vector*) – Projection coordinates.

Returns 3D point coordinates.

Return type *Vector*

class `PhotoScan.CameraGroup`

CameraGroup objects define groups of multiple cameras. The grouping is established by assignment of a CameraGroup instance to the Camera.group attribute of participating cameras.

The type attribute of CameraGroup instances defines the effect of such grouping on processing results and can be set to Folder (no effect) or Station (coincident projection centers).

class **Type**

Camera group type in [Folder, Station]

`CameraGroup.label`
Camera group label.

Type string

`CameraGroup.selected`
Current selection state.

Type boolean

`CameraGroup.type`
Camera group type.

Type *CameraGroup.Type*

class `PhotoScan.CamerasFormat`

Camera orientation format in [CamerasFormatXML, CamerasFormatCHAN, CamerasFormatBoujou, CamerasFormatBundler, CamerasFormatOPK, CamerasFormatPATB, CamerasFormatBINGO, CamerasFormatAeroSys, CamerasFormatInpho, CamerasFormatRZML, CamerasFormatVisionMap]

class `PhotoScan.Chunk`

A Chunk object:

- provides access to all chunk components (sensors, cameras, camera groups, markers, scale bars)
- contains data inherent to individual frames (point cloud, model, etc)
- implements processing methods (matchPhotos, alignCameras, buildDenseCloud, buildModel, etc)
- provides access to other chunk attributes (transformation matrix, coordinate system, meta-data, etc..)

New components can be created using corresponding addXXX methods (addSensor, addCamera, addCameraGroup, addMarker, addScalebar, addFrame). Removal of components is supported by a single remove method, which can accept lists of various component types.

In case of multi-frame chunks the Chunk object contains an additional reference to the particular chunk frame, initialized to the current frame by default. Various methods that work on a per frame basis (matchPhotos, buildModel, etc) are applied to this particular frame. A frames attribute can be used to obtain a list of Chunk objects that reference all available frames.

The following example performs image matching and alignment for the active chunk:

```
>>> import PhotoScan
>>> chunk = PhotoScan.app.document.chunk
>>> for frame in chunk.frames:
...     frame.matchPhotos(accuracy=PhotoScan.HighAccuracy)
>>> chunk.alignCameras()
```

addCamera ([*sensor*])

Add new camera to the chunk.

Parameters **sensor** (*Sensor*) – Sensor to be assigned to this camera.

Returns Created camera.

Return type *Camera*

addCameraGroup ()

Add new camera group to the chunk.

Returns Created camera group.

Return type *CameraGroup*

addFrame ()

Add new frame to the chunk.

Returns Created frame.

Return type *Frame*

addFrames (*chunk*[, *frames*][, *items*][, *progress*])

Add frames from specified chunk.

Parameters

- **chunk** (*PhotoScan.Chunk*) – Chunk to copy frames from.
- **frames** (list of *Frame*) – Optional list of frames to be copied.
- **items** (list of *PhotoScan.DataSource*) – A list of items to copy.
- **progress** (*Callable[[float], None]*) – Progress callback.

addMarker ([*point*], *visibility=False*)

Add new marker to the chunk.

Parameters

- **point** (*PhotoScan.Vector*) – Point to initialize marker projections.
- **visibility** (*boolean*) – Enables visibility check during projection assignment.

Returns Created marker.

Return type *Marker*

addMarkerGroup()

Add new marker group to the chunk.

Returns Created marker group.

Return type *MarkerGroup*

addPhotos(*filenames*[, *layout*][, *progress*])

Add a list of photos to the chunk.

Parameters

- **filenames** (*list of string*) – A list of file paths.
- **layout** (*PhotoScan.ImageLayout*) – Image layout in the chunk.
- **progress** (*Callable[[float], None]*) – Progress callback.

addScalebar(*point1*, *point2*)

Add new scale bar to the chunk.

Parameters

- **point1** (*Marker* or *Camera*) – First endpoint.
- **point2** – Second endpoint.

Returns Created scale bar.

Return type *Scalebar*

addScalebarGroup()

Add new scale bar group to the chunk.

Returns Created scale bar group.

Return type *ScalebarGroup*

addSensor()

Add new sensor to the chunk.

Returns Created sensor.

Return type *Sensor*

alignCameras([*cameras*][, *min_image*], *adaptive_fitting*=True[, *progress*])

Perform photo alignment for the chunk.

Parameters

- **cameras** (list of *Camera*) – A list of cameras to be aligned to the existing cameras.
- **min_image** (*int*) – Minimum number of point projections.
- **adaptive_fitting** (*boolean*) – Enables adaptive fitting of distortion coefficients.
- **progress** (*Callable[[float], None]*) – Progress callback.

buildContours(*source_data*=*ElevationData*, *interval*=1[, *min_value*][, *max_value*][, *progress*])

Build contours for the chunk.

Parameters

- **source_data** (*PhotoScan.DataSource*) – Source data for contour generation.
- **interval** (*float*) – Contour interval.
- **min_value** (*float*) – Minimum value of contour range.

- **max_value** (*float*) – Maximum value of contour range.
- **progress** (*Callable[[float], None]*) – Progress callback.

buildDem (*source=DenseCloudData*, *interpolation=EnabledInterpolation*[, *projection*][, *region*][, *classes*][, *progress*])

Build elevation model for the chunk.

Parameters

- **source** (*PhotoScan.DataSource*) – Selects between dense point cloud and sparse point cloud. If not specified, uses dense cloud if available.
- **interpolation** (*PhotoScan.Interpolation*) – Interpolation mode.
- **projection** (*Matrix* or *CoordinateSystem*) – Sets output projection.
- **region** (*tuple of 4 floats*) – Region to be exported in the (x0, y0, x1, y1) format.
- **classes** (list of *PhotoScan.PointClass*) – List of dense point classes to be used for surface extraction.
- **progress** (*Callable[[float], None]*) – Progress callback.

buildDenseCloud (*quality=MediumQuality*, *filter=AggressiveFiltering*[, *cameras*], *keep_depth=False*, *reuse_depth=False*[, *progress*])

Generate depth maps for the chunk.

Parameters

- **quality** (*PhotoScan.Quality*) – Depth map quality.
- **filter** (*PhotoScan.FilterMode*) – Depth map filtering level.
- **cameras** (list of *Camera*) – A list of cameras to be processed.
- **keep_depth** (*boolean*) – Enables keep depth maps option.
- **reuse_depth** (*boolean*) – Enables reuse depth maps option.
- **progress** (*Callable[[float], None]*) – Progress callback.

buildModel (*surface=Arbitrary*, *interpolation=EnabledInterpolation*, *face_count=MediumFaceCount*[, *source*][, *classes*], *vertex_colors=True*[, *progress*])

Generate model for the chunk frame.

Parameters

- **surface** (*PhotoScan.SurfaceType*) – Type of object to be reconstructed.
- **interpolation** (*PhotoScan.Interpolation*) – Interpolation mode.
- **face_count** (*PhotoScan.FaceCount* or *int*) – Target face count.
- **source** (*PhotoScan.DataSource*) – Selects between dense point cloud and sparse point cloud. If not specified, uses dense cloud if available.
- **classes** (list of *PhotoScan.PointClass*) – List of dense point classes to be used for surface extraction.
- **vertex_colors** (*bool*) – Enables/disables vertex colors calculation.
- **progress** (*Callable[[float], None]*) – Progress callback.

buildOrthomosaic (*surface=ElevationData*, *blending=MosaicBlending*, *color_correction=False*, *fill_holes=True*[, *projection*][, *region*][, *dx*][, *dy*][, *progress*])

Build orthomosaic for the chunk.

Parameters

- **surface** (*PhotoScan.DataSource*) – Orthorectification surface.
- **blending** (*PhotoScan.BlendingMode*) – Orthophoto blending mode.
- **color_correction** (*boolean*) – Enables color correction.
- **fill_holes** (*boolean*) – Enables hole filling.
- **projection** (*Matrix* or *CoordinateSystem*) – Sets output projection.
- **region** (*tuple of 4 floats*) – Region to be exported in the (x0, y0, x1, y1) format.
- **dx** (*float*) – Pixel size in the X dimension in projected units.
- **dy** (*float*) – Pixel size in the Y dimension in projected units.
- **progress** (*Callable[[float], None]*) – Progress callback.

buildPoints (*error=10* [, *min_image*] [, *progress*])
Rebuild point cloud for the chunk.

Parameters

- **error** (*float*) – Reprojection error threshold.
- **min_image** (*int*) – Minimum number of point projections.
- **progress** (*Callable[[float], None]*) – Progress callback.

buildSeamlines (*epsilon=1.5* [, *progress*])
Generate shapes for orthomosaic seamlines.

Parameters

- **epsilon** (*float*) – Contour simplification threshold.
- **progress** (*Callable[[float], None]*) – Progress callback.

buildTexture (*blending=MosaicBlending*, *color_correction=False*, *size=2048*, *fill_holes=True* [, *cameras*] [, *progress*])
Generate texture for the chunk.

Parameters

- **blending** (*PhotoScan.BlendingMode*) – Texture blending mode.
- **color_correction** (*boolean*) – Enables color correction.
- **size** (*int*) – Texture size.
- **fill_holes** (*boolean*) – Enables hole filling.
- **cameras** (list of *Camera*) – A list of cameras to be used for texturing.
- **progress** (*Callable[[float], None]*) – Progress callback.

buildTiledModel ([*pixel_size*], *tile_size=256* [, *source*] [, *progress*])
Build tiled model for the chunk.

Parameters

- **pixel_size** (*float*) – Target model resolution in meters.
- **tile_size** (*int*) – Size of tiles in pixels.
- **source** (*PhotoScan.DataSource*) – Selects between dense point cloud and mesh. If not specified, uses dense cloud if available.

- **progress** (*Callable*[[float], None]) – Progress callback.

buildUV (*mapping*=*GenericMapping*, *count*=1[, *camera*][, *progress*])

Generate uv mapping for the model.

Parameters

- **mapping** (*PhotoScan.MappingMode*) – Texture mapping mode.
- **count** (*int*) – Texture count.
- **camera** (*Camera*) – Camera to be used for texturing in MappingCamera mode.
- **progress** (*Callable*[[float], None]) – Progress callback.

camera_groups

List of camera groups in the chunk.

Type list of *CameraGroup*

camera_location_accuracy

Expected accuracy of camera coordinates in meters.

Type *Vector*

camera_rotation_accuracy

Expected accuracy of camera orientation angles in degrees.

Type *Vector*

cameras

List of cameras in the chunk.

Type list of *Camera*

cir_transform

CIR calibration matrix.

Type *CirTransform*

copy ([*frames*][, *items*][, *progress*])

Make a copy of the chunk.

Parameters

- **frames** (list of *Frame*) – Optional list of frames to be copied.
- **items** (list of *PhotoScan.DataSource*) – A list of items to copy.
- **progress** (*Callable*[[float], None]) – Progress callback.

Returns Copy of the chunk.

Return type *Chunk*

crs

Geographic coordinate system used as a world coordinate system.

Type *CoordinateSystem*

decimateModel (*face_count*[, *progress*])

Decimate the model to the specified face count.

Parameters

- **face_count** (*int*) – Target face count.
- **progress** (*Callable*[[float], None]) – Progress callback.

dense_cloud

Generated dense point cloud for the current frame.

Type *DenseCloud*

depth_maps

Generated depth maps for the current frame.

Type *DepthMaps*

detectMarkers (*type=TargetCircular12bit, tolerance=50, inverted=False, noparity=False* [, *progress*])

Create markers from coded targets.

Parameters

- **type** (*PhotoScan.TargetType*) – Type of targets.
- **tolerance** (*int*) – Detector tolerance (0 - 100).
- **inverted** (*boolean*) – Detect markers on black background.
- **noparity** (*boolean*) – Disable parity checking.
- **progress** (*Callable[[float], None]*) – Progress callback.

elevation

Generated elevation model for the current frame.

Type *Elevation*

enabled

Enables/disables the chunk.

Type *boolean*

estimateImageQuality ([*cameras*] [, *progress*])

Estimate image quality.

Parameters

- **cameras** (list of *Camera*) – Optional list of cameras to be processed.
- **progress** (*Callable[[float], None]*) – Progress callback.

euler_angles

Euler angles triplet used for rotation reference.

Type *EulerAngles*

exportCameras (*path*, *format=CamerasFormatXML* [, *projection*], *rotation_order=RotationOrderXYZ*)

Export point cloud and/or camera positions.

Parameters

- **path** (*string*) – Path to output file.
- **format** (*PhotoScan.CamerasFormat*) – Export format.
- **projection** (*CoordinateSystem*) – Output coordinate system.
- **rotation_order** (*PhotoScan.RotationOrder*) – Rotation order (CHAN format only)

```
exportDem(path[, format][, image_format], raster_transform=RasterTransformNone[, projection][, region][, dx][, dy][, blockw][, blockh], nodata=-32767, write_kml=False, write_world=False, write_scheme=False, tiff_big=False[, progress])
```

Export digital elevation model.

Parameters

- **path** (*string*) – Path to output DEM.
- **format** (*PhotoScan.RasterFormat*) – Export format.
- **image_format** (*PhotoScan.ImageFormat*) – Tile format.
- **raster_transform** (*PhotoScan.RasterTransformType*) – Raster transformation. Can be *RasterTransformNone* or *RasterTransformPalette*.
- **projection** (*CoordinateSystem*) – Output coordinate system.
- **region** (*tuple of 4 floats*) – Region to be exported in the (x0, y0, x1, y1) format.
- **dx** (*float*) – Pixel size in the X dimension in projected units.
- **dy** (*float*) – Pixel size in the Y dimension in projected units.
- **blockw** (*int*) – Specifies block width of the DEM mosaic in pixels.
- **blockh** (*int*) – Specifies block height of the DEM mosaic in pixels.
- **nodata** (*float*) – No-data value.
- **write_kml** (*boolean*) – Enables/disables kml file generation.
- **write_world** (*boolean*) – Enables/disables world file generation.
- **write_scheme** (*boolean*) – Enables/disables tile scheme files generation.
- **tiff_big** (*boolean*) – Enables/disables BigTIFF compression for TIFF files.
- **progress** (*Callable[[float], None]*) – Progress callback.

```
exportMarkers(path[, projection])
```

Export markers.

Parameters

- **path** (*string*) – Path to output file.
- **projection** (*CoordinateSystem*) – Output coordinate system.

```
exportMatches(path, format=MatchesFormatBINGO, precision=3, export_points=True, export_markers=False, use_labels=False[, progress])
```

Export point matches.

Parameters

- **path** (*string*) – Path to output file.
- **format** (*PhotoScan.MatchesFormat*) – Export format.
- **precision** (*int*) – Number of digits after the decimal point.
- **export_points** (*boolean*) – Enables/disables export of automatic tie points.
- **export_markers** (*boolean*) – Enables/disables export of manual matching points.
- **use_labels** (*boolean*) – Enables/disables label based item identifiers.
- **progress** (*Callable[[float], None]*) – Progress callback.

```
exportModel (path, binary=True, precision=6, texture_format=ImageFormat.JPEG, texture=True,
             normals=True, colors=True, cameras=True, markers=True, udim=False,
             strip_extensions=False[, comment][[, format][[, projection][[, shift][[, progress
             ]])
```

Export generated model for the chunk.

Parameters

- **path** (*string*) – Path to output model.
- **binary** (*boolean*) – Enables/disables binary encoding (if supported by format).
- **precision** (*int*) – Number of digits after the decimal point (for text formats).
- **texture_format** (*PhotoScan.ImageFormat*) – Texture format.
- **texture** (*boolean*) – Enables/disables texture export.
- **normals** (*boolean*) – Enables/disables export of vertex normals.
- **colors** (*boolean*) – Enables/disables export of vertex colors.
- **cameras** (*boolean*) – Enables/disables camera export.
- **markers** (*boolean*) – Enables/disables marker export.
- **udim** (*boolean*) – Enables/disables UDIM texture layout.
- **strip_extensions** (*boolean*) – Strips camera label extensions during export.
- **comment** (*string*) – Optional comment (if supported by selected format).
- **format** (*PhotoScan.ModelFormat*) – Export format.
- **projection** (*CoordinateSystem*) – Output coordinate system.
- **shift** (*3-element vector*) – Optional shift to be applied to vertex coordinates.
- **progress** (*Callable[[float], None]*) – Progress callback.

```
exportOrthomosaic (path[, format][[, image_format[, raster_transform=RasterTransformNone[,
             projection][[, region][[, dx][[, dy][[, blockw][[, blockh[, write_kml=False,
             write_world=False, write_scheme=False, write_alpha=True,
             tiff_compression=TiffCompressionLZW, tiff_big=False, jpeg_quality=90,
             white_background=True[, progress ]])
```

Export orthophoto for the chunk.

Parameters

- **path** (*string*) – Path to output orthophoto.
- **format** (*PhotoScan.RasterFormat*) – Export format.
- **image_format** (*PhotoScan.ImageFormat*) – Tile format.
- **raster_transform** (*PhotoScan.RasterTransformType*) – Raster band transformation.
- **projection** (*CoordinateSystem*) – Output coordinate system.
- **region** (*tuple of 4 floats*) – Region to be exported in the (x0, y0, x1, y1) format.
- **dx** (*float*) – Pixel size in the X dimension in projected units.
- **dy** (*float*) – Pixel size in the Y dimension in projected units.
- **blockw** (*int*) – Specifies block width of the orthophoto mosaic in pixels.

- **blockh** (*int*) – Specifies block height of the orthophoto mosaic in pixels.
- **write_kml** (*boolean*) – Enables/disables kml file generation.
- **write_world** (*boolean*) – Enables/disables world file generation.
- **write_scheme** (*boolean*) – Enables/disables tile scheme files generation.
- **write_alpha** (*boolean*) – Enables/disables alpha channel generation.
- **tiff_compression** (*PhotoScan.TiffCompression*) – Tiff compression.
- **tiff_big** (*boolean*) – Enables/disables BigTIFF compression for TIFF files.
- **jpeg_quality** (*int*) – JPEG quality.
- **white_background** (*boolean*) – Enables/disables white background.
- **progress** (*Callable[[float], None]*) – Progress callback.

```
exportOrthophotos (path, raster_transform=RasterTransformNone[], projection[], region[],  
                  dx[], dy[], write_kml=False, write_world=False, write_alpha=True,  
                  tiff_compression=TiffCompressionLZW, tiff_big=False, jpeg_quality=90,  
                  white_background=True[], progress[])
```

Export orthophoto for the chunk.

Parameters

- **path** (*string*) – Path to output orthophoto.
- **raster_transform** (*PhotoScan.RasterTransformType*) – Raster band transformation.
- **projection** (*CoordinateSystem*) – Output coordinate system.
- **region** (*tuple of 4 floats*) – Region to be exported in the (x0, y0, x1, y1) format.
- **dx** (*float*) – Pixel size in the X dimension in projected units.
- **dy** (*float*) – Pixel size in the Y dimension in projected units.
- **write_kml** (*boolean*) – Enables/disables kml file generation.
- **write_world** (*boolean*) – Enables/disables world file generation.
- **write_alpha** (*boolean*) – Enables/disables alpha channel generation.
- **tiff_compression** (*PhotoScan.TiffCompression*) – Tiff compression.
- **tiff_big** (*boolean*) – Enables/disables BigTIFF compression for TIFF files.
- **jpeg_quality** (*int*) – JPEG quality.
- **white_background** (*boolean*) – Enables/disables white background.
- **progress** (*Callable[[float], None]*) – Progress callback.

```
exportPoints (path[], source[], binary=True, precision=6, normals=True, colors=True[], comment[],  
              format[], projection[], shift[], blockw[], blockh[], classes[], progress[])
```

Export point cloud.

Parameters

- **path** (*string*) – Path to output file.
- **source** (*PhotoScan.DataSource*) – Selects between dense point cloud and sparse point cloud. If not specified, uses dense cloud if available.

- **binary** (*boolean*) – Enables/disables binary encoding for selected format (if applicable).
- **precision** (*int*) – Number of digits after the decimal point (for text formats).
- **normals** (*boolean*) – Enables/disables export of point normals.
- **colors** (*boolean*) – Enables/disables export of point colors.
- **comment** (*string*) – Optional comment (if supported by selected format).
- **format** (*PhotoScan.PointsFormat*) – Export format.
- **projection** (*CoordinateSystem*) – Output coordinate system.
- **shift** (*3-element vector*) – Optional shift to be applied to vertex coordinates.
- **blockw** (*float*) – Tile width in meters.
- **blockh** (*float*) – Tile height in meters.
- **classes** (list of *PhotoScan.PointClass*) – List of dense point classes to be exported.
- **progress** (*Callable[[float], None]*) – Progress callback.

exportReport (*path*, [*title*], [*description*], [*settings*], [*progress*])

Export processing report in PDF format.

Parameters

- **path** (*string*) – Path to output report.
- **title** (*string*) – Report title.
- **description** (*string*) – Report description.
- **settings** (list of (*string*, *string*) tuples) – A list of user defined settings to include on the Processing Parameters page.
- **progress** (*Callable[[float], None]*) – Progress callback.

exportShapes (*path*, *items*=*Shape.Polygon*, [*groups*], [*projection*], [*shift*], [*progress*])

Export shapes layer to file.

Parameters

- **path** (*string*) – Path to shape file.
- **items** (*PhotoScan.Shape.Type*) – Items to export.
- **groups** (list of *ShapeGroup*) – A list of shape groups to export.
- **projection** (*CoordinateSystem*) – Output coordinate system.
- **shift** (*3-element vector*) – Optional shift to be applied to vertex coordinates.
- **progress** (*Callable[[float], None]*) – Progress callback.

exportTiledModel (*path*, *format*=*TiledModelFormatTLS*, *mesh_format*=*ModelFormatCOLLADA*, [*progress*])

Export generated tiled model for the chunk.

Parameters

- **path** (*string*) – Path to output model.
- **format** (*PhotoScan.TiledModelFormat*) – Export format.
- **mesh_format** (*PhotoScan.ModelFormat*) – Mesh format for zip export.

- **progress** (*Callable*[[float], None]) – Progress callback.

frame

Current frame index.

Type int

frames

List of frames in the chunk.

Type list of *Frame*

image_brightness

Image brightness as percentage.

Type float

importCameras (*path*, *format*=*CamerasFormatXML*)

Import camera positions.

Parameters

- **path** (*string*) – Path to the file.
- **format** (*PhotoScan.CamerasFormat*) – File format.

importDem (*path*[, *projection*][, *progress*])

Import elevation model from file.

Parameters

- **path** (*string*) – Path to elevation model in GeoTIFF format.
- **projection** (*CoordinateSystem*) – Default coordinate system if not specified in GeoTIFF file.
- **progress** (*Callable*[[float], None]) – Progress callback.

importMarkers (*path*)

Import markers.

Parameters **path** (*string*) – Path to the file.

importMasks (*path*='', *source*=*MaskSourceAlpha*, *operation*=*MaskOperationReplacement*, *tolerance*=10[, *cameras*][, *progress*])

Import masks for multiple cameras.

Parameters

- **path** (*string*) – Mask file name template.
- **source** (*PhotoScan.MaskSource*) – Mask source.
- **operation** (*PhotoScan.MaskOperation*) – Mask operation.
- **tolerance** (*int*) – Background masking tolerance.
- **cameras** (list of *Camera*) – Optional list of cameras to be processed.
- **progress** (*Callable*[[float], None]) – Progress callback.

importModel (*path*[, *format*][, *projection*][, *shift*][, *progress*])

Import model from file.

Parameters

- **path** (*string*) – Path to model.
- **format** (*PhotoScan.ModelFormat*) – Model format.

- **projection** (*CoordinateSystem*) – Model coordinate system.
- **shift** (*3-element vector*) – Optional shift to be applied to vertex coordinates.
- **progress** (*Callable[[float], None]*) – Progress callback.

importShapes (*path*='', *replace*=False, *boundary*=*Shape.NoBoundary*)

Import shapes layer from file.

Parameters

- **path** (*string*) – Path to shape file.
- **replace** (*boolean*) – Replace current shapes with new data.
- **boundary** (*Shape.BoundaryType*) – Boundary type to be applied to imported shapes.

key

Chunk identifier.

Type int

label

Chunk label.

Type string

loadReference (*path*[, *format*], *columns*='nxyzabc', *delimiter*=' ', *group_delimiters*=False, *skip_rows*=0)

Import reference data from the specified file.

Parameters

- **path** (*string*) – Path to the file with reference data.
- **format** (*PhotoScan.ReferenceFormat*) – File format.
- **columns** (*string*) – column order in csv format (n - label, o - enabled flag, x/y/z - coordinates, X/Y/Z - coordinate accuracy, a/b/c - rotation angles, A/B/C - rotation angle accuracy, [] - group of multiple values, | - column separator within group)
- **delimiter** (*string*) – column delimiter in csv format
- **group_delimiters** (*boolean*) – combine consecutive delimiters in csv format
- **skip_rows** (*int*) – number of rows to skip in csv format

Example

```
>>> loadReference('reference.csv', 'nxyz[XYZ]abc[ABC]')
>>> loadReference('reference.csv', '[n|x|y|z|XYZ|a|b|c|ABC]')
```

loadReferenceExif (*load_rotation*=False, *load_accuracy*=False)

Import camera locations from EXIF meta data.

Parameters

- **load_rotation** (*boolean*) – load yaw, pitch and roll orientation angles.
- **load_accuracy** (*boolean*) – load camera location accuracy.

marker_groups

List of marker groups in the chunk.

Type list of *MarkerGroup*

marker_location_accuracy

Expected accuracy of marker coordinates in meters.

Type *Vector*

marker_projection_accuracy

Expected accuracy of marker projections in pixels.

Type *float*

markers

List of markers in the chunk.

Type list of *Marker*

masks

Image masks.

Type *Masks*

master_channel

Master channel index (-1 for default).

Type *int*

matchPhotos (*accuracy=HighAccuracy*, *preselection=ReferencePreselection*,
generic_preselection=True, *reference_preselection=True*, *filter_mask=False*, *key-*
point_limit=40000, *tiepoint_limit=4000*[, *pairs*][, *progress*])

Perform image matching for the chunk frame.

Parameters

- **accuracy** (*PhotoScan.Accuracy*) – Alignment accuracy.
- **preselection** (*PhotoScan.Preselection*) – Image pair preselection method (obsolete).
- **generic_preselection** (*boolean*) – Enables generic image pair preselection.
- **reference_preselection** (*boolean*) – Enables reference image pair preselection.
- **filter_mask** (*boolean*) – Filter points by mask.
- **keypoint_limit** (*int*) – Maximum number of key points to look for in each photo.
- **tiepoint_limit** (*int*) – Maximum number of tie points to generate for each photo.
- **pairs** (list of *PhotoScan.Camera* tuples) – User defined list of camera pairs to match.
- **progress** (*Callable[[float], None]*) – Progress callback.

meta

Chunk meta data.

Type *MetaData*

model

Generated model for the current frame.

Type *Model*

optimizeCameras (*fit_f=True*, *fit_cx=True*, *fit_cy=True*, *fit_b1=True*, *fit_b2=True*, *fit_k1=True*,
fit_k2=True, *fit_k3=True*, *fit_k4=False*, *fit_p1=True*, *fit_p2=True*, *fit_p3=False*,
fit_p4=False, *fit_shutter=False*[, *progress*])

Perform optimization of point cloud / camera parameters.

Parameters

- **fit_f** (*boolean*) – Enables optimization of focal length coefficient.
- **fit_cx** (*boolean*) – Enables optimization of X principal point coordinates.
- **fit_cy** (*boolean*) – Enables optimization of Y principal point coordinates.
- **fit_b1** (*boolean*) – Enabled optimization of aspect ratio.
- **fit_b2** (*boolean*) – Enables optimization of skew coefficient.
- **fit_k1** (*boolean*) – Enables optimization of k1 radial distortion coefficient.
- **fit_k2** (*boolean*) – Enables optimization of k2 radial distortion coefficient.
- **fit_k3** (*boolean*) – Enables optimization of k3 radial distortion coefficient.
- **fit_k4** (*boolean*) – Enables optimization of k4 radial distortion coefficient.
- **fit_p1** (*boolean*) – Enables optimization of p1 tangential distortion coefficient.
- **fit_p2** (*boolean*) – Enables optimization of p2 tangential distortion coefficient.
- **fit_p3** (*boolean*) – Enables optimization of p3 tangential distortion coefficient.
- **fit_p4** (*boolean*) – Enables optimization of p4 tangential distortion coefficient.
- **fit_shutter** (*boolean*) – Enables optimization of rolling shutter compensation parameters.
- **progress** (*Callable[[float], None]*) – Progress callback.

orthomosaic

Generated orthomosaic for the current frame.

Type *Orthomosaic*

point_cloud

Generated sparse point cloud.

Type *PointCloud*

raster_transform

Raster transform.

Type *RasterTransform*

refineMarkers (*[markers][, progress]*)

Refine markers based on images content.

Parameters

- **markers** (list of *Marker*) – Optional list of markers to be processed.
- **progress** (*Callable[[float], None]*) – Progress callback.

region

Reconstruction volume selection.

Type *Region*

remove (*items*)

Remove items from the chunk.

Parameters **items** (list of *Frame*, *Sensor*, *CameraGroup*, *MarkerGroup*, *ScalebarGroup*, *Camera*, *Marker* or *Scalebar*) – A list of items to be removed.

resetRegion()

Reset reconstruction volume selector to default position.

saveReference (*path*[, *format*], *items*=*ReferenceItemsCameras*[, *columns*], *delimiter*=' ')

Export reference data to the specified file.

Parameters

- **path** (*string*) – Path to the output file.
- **format** (*PhotoScan.ReferenceFormat*) – Export format.
- **items** (*PhotoScan.ReferenceItems*) – Items to export in CSV format.
- **columns** (*string*) – column order in csv format (n - label, o - enabled flag, x/y/z - coordinates, X/Y/Z - coordinate accuracy, a/b/c - rotation angles, A/B/C - rotation angle accuracy, u/v/w - estimated coordinates, U/V/W - coordinate errors, d/e/f - estimated orientation angles, D/E/F - orientation errors, [] - group of multiple values, | - column separator within group)
- **delimiter** (*string*) – column delimiter in csv format

scalebar_accuracy

Expected scale bar accuracy in meters.

Type float

scalebar_groups

List of scale bar groups in the chunk.

Type list of *ScalebarGroup*

scalebars

List of scale bars in the chunk.

Type list of *Scalebar*

selected

Selects/deselects the chunk.

Type boolean

sensors

List of sensors in the chunk.

Type list of *Sensor*

shapes

Shapes for the current frame.

Type *Shapes*

smoothModel (*strength* = 3[, *progress*])

Smooth mesh using Laplacian smoothing algorithm.

Parameters

- **strength** (*float*) – Smoothing strength.
- **progress** (*Callable*[[*float*], *None*]) – Progress callback.

thinPointCloud (*point_limit*=1000)

Remove excessive tracks from the point cloud.

Parameters **point_limit** (*int*) – Maximum number of points for each photo.

thumbnails

Image thumbnails.

Type *Thumbnails***tiepoint_accuracy**

Expected tie point accuracy in pixels.

Type float**tiled_model**

Generated tiled model for the current frame.

Type *TiledModel***trackMarkers** ([start][, end][, progress])

Track marker projections through the frame sequence.

Parameters

- **start** (*int*) – Starting frame index.
- **end** (*int*) – Ending frame index.
- **progress** (*Callable[[float], None]*) – Progress callback.

transform

4x4 matrix specifying chunk location in the world coordinate system.

Type *ChunkTransform***updateTransform()**

Update chunk transformation based on reference data.

class PhotoScan.**ChunkTransform**

Transformation between chunk and world coordinates systems.

matrix

Transformation matrix.

Type *Matrix***rotation**

Rotation component.

Type *Matrix***scale**

Scale component.

Type float**translation**

Translation component.

Type *Vector***class** PhotoScan.**CirTransform**

CIR calibration matrix.

calibrate()

Calibrate CIR matrix based on orthomosaic histogram.

coeffs

Color matrix.

Type *Matrix*

reset ()

Reset CIR calibration matrix.

class PhotoScan.CoordinateSystem

Coordinate reference system (local, geographic or projected).

The following example changes chunk coordinate system to WGS 84 / UTM zone 41N and loads reference data from file:

```
>>> import PhotoScan
>>> chunk = PhotoScan.app.document.chunk
>>> chunk.crs = PhotoScan.CoordinateSystem("EPSG:32641")
>>> chunk.loadReference("gcp.txt", PhotoScan.ReferenceFormatCSV)
>>> chunk.updateTransform()
```

authority

Authority identifier of the coordinate system.

Type string

geogcs

Base geographic coordinate system.

Type *CoordinateSystem*

init (crs)

Initialize projection based on specified WKT definition or authority identifier.

Parameters **crs** (*string*) – WKT definition of coordinate system or authority identifier.

listBuiltinCRS ()

Returns a list of builtin coordinate systems.

localframe (point)

Returns 4x4 transformation matrix to LSE coordinates at the given point.

Parameters **point** (*Vector*) – Coordinates of the origin in the geocentric coordinates.

Returns Transformation from geocentric coordinates to local coordinates.

Return type *Matrix*

name

Name of the coordinate system.

Type string

proj4

Coordinate system definition in PROJ.4 format.

Type string

project (point)

Projects point from geocentric coordinates to projected geographic coordinate system.

Parameters **point** (*Vector*) – 3D point in geocentric coordinates.

Returns 3D point in projected coordinates.

Return type *Vector*

transform (point, source, target)

Transform point coordinates between coordinate systems.

Parameters

- **point** (2 or 3 component *Vector*) – Point coordinates.
- **source** (*CoordinateSystem*) – Source coordinate system.
- **target** (*CoordinateSystem*) – Target coordinate system.

Returns Transformed point coordinates.

Return type *Vector*

unproject (*point*)

Unprojects point from projected coordinates to geocentric coordinates.

Parameters **point** (*Vector*) – 3D point in projected coordinate system.

Returns 3D point in geocentric coordinates.

Return type *Vector*

wkt

Coordinate system definition in WKT format.

Type string

class `PhotoScan.DataSource`

Data source in [PointCloudData, DenseCloudData, DepthMapsData, ModelData, TiledModelData, ElevationData, OrthomosaicData]

class `PhotoScan.DenseCloud`

Dense point cloud data.

assignClass (*target=0* [, *source*] [, *progress*])

Assign class to points.

Parameters

- **target** (*PhotoScan.PointClass*) – Target class.
- **source** (*PhotoScan.PointClass* or list of *PhotoScan.PointClass*) – Classes of points to be replaced.
- **progress** (*Callable*[[*float*], *None*]) – Progress callback.

assignClassToSelection (*target=0* [, *source*] [, *progress*])

Assign class to selected points.

Parameters

- **target** (*PhotoScan.PointClass*) – Target class.
- **source** (*PhotoScan.PointClass* or list of *PhotoScan.PointClass*) – Classes of points to be replaced.
- **progress** (*Callable*[[*float*], *None*]) – Progress callback.

classifyGroundPoints (*max_angle=15.0*, *max_distance=1.0*, *cell_size=50.0* [, *source*] [, *progress*])

Classify points into ground and non ground classes.

Parameters

- **max_angle** (*float*) – Maximum angle (degrees).
- **max_distance** (*float*) – Maximum distance (meters).
- **cell_size** (*float*) – Cell size (meters).
- **source** (*PhotoScan.PointClass*) – Class of points to be re-classified.

- **progress** (*Callable*[[float], None]) – Progress callback.

compactPoints ([*progress*])
Permanently removes deleted points from dense cloud.

Parameters **progress** (*Callable*[[float], None]) – Progress callback.

copy ()
Returns a copy of the dense cloud.

Returns Copy of the dense cloud.

Return type *DenseCloud*

cropSelectedPoints ([*point_classes*][, *progress*])
Crop selected points.

Parameters

- **point_classes** (*PhotoScan.PointClass* or list of *PhotoScan.PointClass*) – Classes of points to be removed.
- **progress** (*Callable*[[float], None]) – Progress callback.

meta
Dense cloud meta data.

Type *MetaData*

pickPoint (*origin*, *target*)
Returns ray intersection with the point cloud (point on the ray nearest to some point).

Parameters

- **origin** (*PhotoScan.Vector*) – Ray origin.
- **target** (*PhotoScan.Vector*) – Point on the ray.

Returns Coordinates of the intersection point.

Return type *PhotoScan.Vector*

point_count
Number of points in dense cloud.

Type int

removePoints (*point_classes*[, *progress*])
Remove points.

Parameters

- **point_classes** (*PhotoScan.PointClass* or list of *PhotoScan.PointClass*) – Classes of points to be removed.
- **progress** (*Callable*[[float], None]) – Progress callback.

removeSelectedPoints ([*point_classes*][, *progress*])
Remove selected points.

Parameters

- **point_classes** (*PhotoScan.PointClass* or list of *PhotoScan.PointClass*) – Classes of points to be removed.
- **progress** (*Callable*[[float], None]) – Progress callback.

restorePoints (*[point_classes]*, *progress*)

Restore deleted points.

Parameters

- **point_classes** (*PhotoScan.PointClass* or list of *PhotoScan.PointClass*) – Classes of points to be restored.
- **progress** (*Callable[[float], None]*) – Progress callback.

selectMaskedPoints (*cameras*, *softness=4*, *progress*)

Select dense points based on image masks.

Parameters

- **cameras** (list of *Camera*) – A list of cameras to use for selection.
- **softness** (*float*) – Mask edge softness.
- **progress** (*Callable[[float], None]*) – Progress callback.

selectPointsByColor (*color*, *tolerance=10*, *channels='RGB'*, *progress*)

Select dense points based on point colors.

Parameters

- **color** (*list of int*) – Color to select.
- **tolerance** (*int*) – Color tolerance.
- **channels** (*string*) – Combination of color channels to compare in ['R', 'G', 'B', 'H', 'S', 'V'].
- **progress** (*Callable[[float], None]*) – Progress callback.

updateStatistics (*progress*)

Updates dense cloud statistics.

Parameters **progress** (*Callable[[float], None]*) – Progress callback.

class *PhotoScan.DepthMap*

Depth map data.

calibration

Depth map calibration.

Type *Calibration*

copy ()

Returns a copy of the depth map.

Returns Copy of the depth map.

Return type *DepthMap*

image ()

Returns image data.

Returns Image data.

Return type *Image*

setImage (*image*)

Parameters **image** (*Image*) – Image object with depth map data.

class *PhotoScan.DepthMaps*

A set of depth maps generated for a chunk frame.

items()

List of items.

keys()

List of item keys.

meta

Depth maps meta data.

Type *MetaData*

values()

List of item values.

class *PhotoScan.Document*

PhotoScan project.

Contains list of chunks available in the project. Implements processing operations that work with multiple chunks. Supports saving/loading project files.

The project currently opened in PhotoScan window can be accessed using *PhotoScan.app.document* attribute. Additional Document objects can be created as needed.

The following example saves active chunk from the opened project in a separate project:

```
>>> import PhotoScan
>>> doc = PhotoScan.app.document
>>> doc.save(path = "project.psz", chunks = [doc.chunk])
```

addChunk()

Add new chunk to the document.

Returns Created chunk.

Return type *Chunk*

alignChunks (*chunks*, *reference*, *method*='points', *fix_scale*=False, *accuracy*=*HighAccuracy*, *preselection*=False, *filter_mask*=False, *point_limit*=40000[, *progress*])

Align specified set of chunks.

Parameters

- **chunks** (*list*) – List of chunks to be aligned.
- **reference** (*Chunk*) – Chunk to be used as a reference.
- **method** (*string*) – Alignment method in ['points', 'markers', 'cameras'].
- **fix_scale** (*boolean*) – Fixes chunk scale during alignment.
- **accuracy** (*PhotoScan.Accuracy*) – Alignment accuracy.
- **preselection** (*boolean*) – Enables image pair preselection.
- **filter_mask** (*boolean*) – Filter points by mask.
- **point_limit** (*int*) – Maximum number of points for each photo.
- **progress** (*Callable[[float], None]*) – Progress callback.

append (*document*[, *chunks*][, *progress*])

Append the specified Document object to the current document.

Parameters

- **document** (*Document*) – Document object to be appended.

- **chunks** (list of *Chunk*) – List of chunks to append.
- **progress** (*Callable*[[*float*], *None*]) – Progress callback.

chunk

Active Chunk.

Type *Chunk*

chunks

List of chunks in the document.

Type *Chunks*

clear()

Clear the contents of the Document object.

mergeChunks (*chunks*, *merge_dense_clouds*=*False*, *merge_models*=*False*, *merge_markers*=*False*[, *progress*])

Merge specified set of chunks.

Parameters

- **chunks** (*list*) – List of chunks to be merged.
- **merge_dense_clouds** (*boolean*) – Enables/disables merging of dense clouds.
- **merge_models** (*boolean*) – Enables/disables merging of polygonal models.
- **merge_markers** (*boolean*) – Enables/disables merging of corresponding marker across the chunks.
- **progress** (*Callable*[[*float*], *None*]) – Progress callback.

meta

Document meta data.

Type *MetaData*

open(path)

Load document from the specified file.

Parameters **path** (*string*) – Path to the file.

path

Path to the document file.

Type *string*

remove(items)

Remove a set of items from the document.

Parameters **items** (list of *Chunk*) – A list of items to be removed.

save ([*path*][, *chunks*], *compression* = 6, *absolute_paths* = *False*[, *version*])

Save document to the specified file.

Parameters

- **path** (*string*) – Optional path to the file.
- **chunks** (list of *Chunk*) – List of chunks to be saved.
- **compression** (*int*) – Project compression level.
- **absolute_paths** (*boolean*) – Store absolute image paths.
- **version** (*string*) – Project version to save.

class PhotoScan.**Elevation**

Digital elevation model.

altitude (*point*)

Return elevation value at the specified point.

Parameters **point** (*PhotoScan.Vector*) – Point coordinates in the levation coordinate system.

Returns Elevation value.

Return type float

bottom

Y coordinate of the bottom side.

Type float

crs

Coordinate system of elevation model.

Type *CoordinateSystem*

height

Elevation model height.

Type int

left

X coordinate of the left side.

Type float

max

Maximum elevation value.

Type float

meta

Elevation model meta data.

Type *MetaData*

min

Minimum elevation value.

Type float

resolution

DEM resolution in meters.

Type float

right

X coordinate of the right side.

Type float

top

Y coordinate of the top side.

Type float

width

Elevation model width.

Type int

class PhotoScan.**EulerAngles**
Euler angles in [EulerAnglesYPR, EulerAnglesOPK]

class PhotoScan.**FaceCount**
Face count in [LowFaceCount, MediumFaceCount, HighFaceCount]

class PhotoScan.**FilterMode**
Depth filtering mode in [NoFiltering, MildFiltering, ModerateFiltering, AggressiveFiltering]

class PhotoScan.**Image** (*width, height, channels, datatype='U8'*)
1 or 3-channel image

Parameters

- **width** (*int*) – image width
- **height** (*int*) – image height
- **channels** (*string*) – color channel layout, e.g. 'RGB', 'RGBA', etc.

channels
Channel mapping for the image.

Type string

cn
Number of color channels.

Type int

convert (*channels[, datatype]*)
Convert image to specified data type and channel layout.

Parameters

- **channels** (*string*) – color channels to be loaded, e.g. 'RGB', 'RGBA', etc.
- **datatype** (*string*) – pixel data type in ['U8', 'U16', 'U32', 'F32', 'F64']

Returns Converted image.

Return type *Image*

copy ()
Return a copy of the image.

Returns copy of the image

Return type *Image*

data_type
Data type used to store pixel values.

Type string

fromstring (*data, width, height, channels, datatype='U8'*)
Create image from byte array.

Parameters

- **data** (*string*) – raw image data
- **width** (*int*) – image width
- **height** (*int*) – image height
- **channels** (*string*) – color channel layout, e.g. 'RGB', 'RGBA', etc.

- **datatype** (*string*) – pixel data type in ['U8', 'U16', 'U32', 'F32', 'F64']

Returns Created image.

Return type *Image*

height

Image height.

Type *int*

open (*path*, *layer=0*, *datatype='U8'* [, *channels*])

Load image from file.

Parameters

- **path** (*string*) – path to the image file
- **layer** (*int*) – image layer in case of multipage file
- **datatype** (*string*) – pixel data type in ['U8', 'U16', 'U32', 'F32', 'F64']
- **channels** (*string*) – color channels to be loaded, e.g. 'RGB', 'RGBA', etc.

Returns Loaded image.

Return type *Image*

resize (*width*, *height*)

Resize image to specified dimensions.

Parameters

- **width** (*int*) – new image width
- **height** (*int*) – new image height

Returns resized image

Return type *Image*

save (*path*)

Save image to the file.

Parameters **path** (*string*) – path to the image file

Returns success of operation

Return type *boolean*

tostring ()

Convert image to byte array.

Returns Raw image data.

Return type *string*

undistort (*calib*, *center_principal_point = True*, *square_pixels = True*)

Undistort image using provided calibration.

Parameters

- **calib** (*Calibration*) – lens calibration
- **center_principal_point** (*boolean*) – moves principal point to the image center
- **square_pixels** (*boolean*) – create image with square pixels

Returns undistorted image

Return type *Image*

warp (*calib0*, *trans0*, *calib1*, *trans1*)

Warp image by rotating virtual viewpoint.

Parameters

- **calib0** (*Calibration*) – initial calibration
- **trans0** (*Matrix*) – initial camera orientation as 4x4 matrix
- **calib1** (*Calibration*) – final calibration
- **trans1** (*Matrix*) – final camera orientation as 4x4 matrix

Returns warped image

Return type *Image*

width

Image width.

Type int

class PhotoScan.**ImageFormat**

Image format in [ImageFormatJPEG, ImageFormatTIFF, ImageFormatPNG, ImageFormatBMP, ImageFormatEXR, ImageFormatPNM, ImageFormatSGI, ImageFormatCR2, ImageFormatSEQ, ImageFormatARA, ImageFormatTGA]

class PhotoScan.**ImageLayout**

Image layout in [FlatLayout, MultiframeLayout, MultiplaneLayout]

class PhotoScan.**Interpolation**

Interpolation mode in [DisabledInterpolation, EnabledInterpolation, Extrapolated]

class PhotoScan.**MappingMode**

UV mapping mode in [GenericMapping, OrthophotoMapping, AdaptiveOrthophotoMapping, SphericalMapping, CameraMapping]

class PhotoScan.**Marker**

Marker instance

class Projection

Marker projection.

coord

Point coordinates in pixels.

Type *Vector*

pinned

Pinned flag.

Type boolean

class Marker.**Projections**

Collection of projections specified for the marker

items ()

List of items.

keys ()

List of item keys.

values ()

List of item values.

class `Marker.Reference`

Marker reference data.

accuracy

Marker location accuracy.

Type *Vector*

enabled

Enabled flag.

Type `boolean`

location

Marker coordinates.

Type *Vector*

`Marker.frames`

Marker frames.

Type list of *Marker*

`Marker.group`

Marker group.

Type *MarkerGroup*

`Marker.key`

Marker identifier.

Type `int`

`Marker.label`

Marker label.

Type `string`

`Marker.meta`

Marker meta data.

Type *MetaData*

`Marker.position`

Marker position in the current frame.

Type *Vector*

`Marker.projections`

List of marker projections.

Type *MarkerProjections*

`Marker.reference`

Marker reference data.

Type *MarkerReference*

`Marker.selected`

Selects/deselects the marker.

Type `boolean`

class `PhotoScan.MarkerGroup`

MarkerGroup objects define groups of multiple markers. The grouping is established by assignment of a *MarkerGroup* instance to the *Marker.group* attribute of participating markers.

label
Marker group label.

Type string

selected
Current selection state.

Type boolean

class PhotoScan.**Mask**
Mask instance

copy()
Returns a copy of the mask.
Returns Copy of the mask.
Return type *Mask*

image()
Returns image data.
Returns Image data.
Return type *Image*

invert()
Create inverted copy of the mask.
Returns Inverted copy of the mask.
Return type *Mask*

load(*path*[, *layer*])
Loads mask from file.
Parameters

- **path** (*string*) – Path to the image file to be loaded.
- **layer** (*int*) – Optional layer index in case of multipage files.

setImage(*image*)
Parameters **image** (*Image*) – Image object with mask data.

class PhotoScan.**MaskOperation**
Mask operation in [MaskOperationReplacement, MaskOperationUnion, MaskOperationIntersection, MaskOperationDifference]

class PhotoScan.**MaskSource**
Mask source in [MaskSourceAlpha, MaskSourceFile, MaskSourceBackground, MaskSourceModel]

class PhotoScan.**Masks**
A set of masks for a chunk frame.

items()
List of items.

keys()
List of item keys.

meta
Thumbnails meta data.
Type *MetaData*

values ()
List of item values.

class PhotoScan.**MatchesFormat**
Matches format in [MatchesFormatBINGO, MatchesFormatORIMA, MatchesFormatPATB]

class PhotoScan.**Matrix**
m-by-n matrix

```
>>> import PhotoScan
>>> m1 = PhotoScan.Matrix.diag( (1,2,3,4) )
>>> m3 = PhotoScan.Matrix( [[1,2,3,4], [1,2,3,4], [1,2,3,4], [1,2,3,4]] )
>>> m2 = m1.inv()
>>> m3 = m1 * m2
>>> x = m3.det()
>>> if x == 1:
...     PhotoScan.app.messageBox("Diagonal matrix dimensions: " + str(m3.size))
```

Diag (*vector*)
Create a diagonal matrix.

Parameters **vector** (*Vector* or list of floats) – The vector of diagonal entries.

Returns A diagonal matrix.

Return type *Matrix*

Rotation (*matrix*)
Create a rotation matrix.

Parameters **matrix** (*Matrix*) – The 3x3 rotation matrix.

Returns 4x4 matrix representing rotation.

Return type *Matrix*

Scale (*scale*)
Create a scale matrix.

Parameters **scale** (*Vector*) – The scale vector.

Returns A matrix representing scale.

Return type *Matrix*

Translation (*vector*)
Create a translation matrix.

Parameters **vector** (*Vector*) – The translation vector.

Returns A matrix representing translation.

Return type *Matrix*

col (*index*)
Returns column of the matrix.

Returns matrix column.

Return type *Vector*

copy ()
Returns a copy of this matrix.

Returns an instance of itself

Return type *Matrix*

det ()

Return the determinant of a matrix.

Returns Return a the determinant of a matrix.

Return type float

inv ()

Returns an inverted copy of the matrix.

Returns inverted matrix.

Return type *Matrix*

mulp (*point*)

Transforms a point in homogeneous coordinates.

Parameters **point** (*Vector*) – The point to be transformed.

Returns transformed point.

Return type *Vector*

mulv (*vector*)

Transforms vector in homogeneous coordinates.

Parameters **vector** (*Vector*) – The vector to be transformed.

Returns transformed vector.

Return type *Vector*

rotation ()

Returns rotation component of the 4x4 matrix.

Returns rotation component

Return type *Matrix*

row (*index*)

Returns row of the matrix.

Returns matrix row.

Return type *Vector*

scale ()

Returns scale component of the 4x4 matrix.

Returns scale component

Return type float

size

Matrix dimensions.

Type tuple

svd ()

Returns singular value decomposition of the matrix.

Returns u, s, v tuple where $a = u * \text{diag}(s) * v$

Return type *PhotoScan.Matrix PhotoScan.Vector PhotoScan.Matrix* tuple

t ()

Return a new, transposed matrix.

Returns a transposed matrix**Return type** *Matrix***translation ()**

Returns translation component of the 4x4 matrix.

Returns translation component**Return type** *Vector***zero ()**

Set all matrix elements to zero.

class PhotoScan.**MetaData** (*object*)

Collection of object properties

items ()

List of items.

keys ()

List of item keys.

values ()

List of item values.

class PhotoScan.**Model**

Triangular mesh model instance

class **Face**

Triangular face of the model

hidden

Face visibility flag.

Type boolean**selected**

Face selection flag.

Type boolean**tex_vertices**

Texture vertex indices.

Type tuple of 3 int**vertices**

Vertex indices.

Type tuple of 3 int**class** Model.**Faces**

Collection of model faces

class Model.**Statistics**

Mesh statistics

components

Number of connected components.

Type int**degenerate_faces**

Number of degenerate faces.

Type int

duplicate_faces
Number of duplicate faces.
Type int

faces
Total number of faces.
Type int

flipped_normals
Number of edges with flipped normals.
Type int

free_vertices
Number of free vertices.
Type int

multiple_edges
Number of edges connecting more than 2 faces.
Type int

open_edges
Number of open edges.
Type int

out_of_range_indices
Number of out of range indices.
Type int

similar_vertices
Number of similar vertices.
Type int

vertices
Total number of vertices.
Type int

zero_faces
Number of zero faces.
Type int

class `Model.TexVertex`
Texture vertex of the model

coord
Vertex coordinates.
Type tuple of 2 float

class `Model.TexVertices`
Collection of model texture vertices

class `Model.Vertex`
Vertex of the model

color
Vertex color.
Type tuple of 3 int

coord
Vertex coordinates.
Type *Vector*

class `Model.Vertices`

Collection of model vertices

`Model.area()`

Return area of the model surface.

Returns Model area.

Return type float

`Model.closeHoles(level = 30)`

Fill holes in the model surface.

Parameters `level` (*int*) – Hole size threshold in percents.

`Model.copy()`

Create a copy of the model.

Returns Copy of the model.

Return type *Model*

`Model.cropSelection()`

Crop selected faces and free vertices from the mesh.

`Model.faces`

Collection of mesh faces.

Type *MeshFaces*

`Model.fixTopology()`

Remove polygons causing topological problems.

`Model.loadTexture(path)`

Load texture from the specified file.

Parameters `path` (*string*) – Path to the image file.

`Model.meta`

Model meta data.

Type *MetaData*

`Model.pickPoint(origin, target)`

Return ray intersection with mesh.

Parameters

- **origin** (*PhotoScan.Vector*) – Ray origin.
- **target** (*PhotoScan.Vector*) – Point on the ray.

Returns Coordinates of the intersection point.

Return type *PhotoScan.Vector*

`Model.removeComponents(size)`

Remove small connected components.

Parameters `size` (*int*) – Threshold on the polygon count of the components to be removed.

`Model.removeSelection()`

Remove selected faces and free vertices from the mesh.

`Model.renderDepth(transform, calibration)`

Render model depth image for specified viewpoint.

Parameters

- **transform** (*Matrix*) – Camera location.
- **calibration** (*Calibration*) – Camera calibration.

Returns Rendered image.

Return type *Image*

`Model.renderImage(transform, calibration)`

Render model image for specified viewpoint.

Parameters

- **transform** (*Matrix*) – Camera location.
- **calibration** (*Calibration*) – Camera calibration.

Returns Rendered image.

Return type *Image*

`Model.renderMask(transform, calibration)`

Render model mask image for specified viewpoint.

Parameters

- **transform** (*Matrix*) – Camera location.
- **calibration** (*Calibration*) – Camera calibration.

Returns Rendered image.

Return type *Image*

`Model.renderNormalMap(transform, calibration)`

Render image with model normals for specified viewpoint.

Parameters

- **transform** (*Matrix*) – Camera location.
- **calibration** (*Calibration*) – Camera calibration.

Returns Rendered image.

Return type *Image*

`Model.saveTexture(path)`

Save texture to the specified file.

Parameters **path** (*string*) – Path to the image file.

`Model.setTexture(image, page=0)`

Initialize texture from image data.

Parameters

- **image** (*Image*) – Texture image.
- **page** (*int*) – Texture index for multitextured models.

`Model.statistics([progress])`

Return mesh statistics.

Parameters **progress** (*Callable[[float], None]*) – Progress callback.

Returns Mesh statistics.

Return type *Model.Statistics*

Model.tex_vertices

Collection of mesh texture vertices.

Type MeshTexVertices

Model.texture (*page=0*)

Return texture image.

Parameters **page** (*int*) – Texture index for multitextured models.

Returns Texture image.

Return type *Image*

Model.vertices

Collection of mesh vertices.

Type MeshVertices

Model.volume ()

Return volume of the closed model surface.

Returns Model volume.

Return type float

class PhotoScan.**ModelFormat**

Model format in [ModelFormatOBJ, ModelFormat3DS, ModelFormatVRML, ModelFormatPLY, ModelFormatCOLLADA, ModelFormatU3D, ModelFormatPDF, ModelFormatDXF, ModelFormatFBX, ModelFormatKMZ, ModelFormatCTM, ModelFormatSTL, ModelFormatDXF_3DF, ModelFormatTLS]

class PhotoScan.**ModelViewMode**

Model view mode in [ShadedModelView, SolidModelView, WireframeModelView, TexturedModelView]

class PhotoScan.**NetworkClient**

NetworkClient class provides access to the network processing server and allows to create and manage tasks.

The following example connects to the server and lists active tasks:

```
>>> import PhotoScan
>>> client = PhotoScan.NetworkClient()
>>> client.connect('127.0.0.1')
>>> client.batchList()
```

abortBatch (*batch_id*)

Abort batch.

Parameters **batch_id** (*int*) – Batch id.

abortNode (*node_id*)

Abort node.

Parameters **node_id** (*int*) – Node id.

batchList (*revision=0*)

Get list of batches.

Parameters **revision** (*int*) – First revision to get.

Returns List of batches.

Return type dict

batchStatus (*batch_id*, *revision=0*)

Get batch status.

Parameters

- **batch_id** (*int*) – Batch id.
- **revision** (*int*) – First revision to get.

Returns Batch status.

Return type dict

connect (*host*, *port=5840*)

Connect to the server.

Parameters

- **host** (*string*) – Server hostname.
- **port** (*int*) – Communication port.

createBatch (*path*, *tasks*)

Create new batch.

Parameters

- **path** (*string*) – Project path relative to root folder.
- **tasks** (list of *NetworkTask*) – Project path relative to root folder.

Returns Batch id.

Return type int

disconnect ()

Disconnect from the server.

findBatch (*path*)

Get batch id based on project path.

Parameters **path** (*string*) – Project path relative to root folder.

Returns Batch id.

Return type int

nodeList ()

Get list of active nodes.

Returns List of nodes.

Return type list

nodeStatus (*node_id*, *revision=0*)

Get node status.

Parameters

- **node_id** (*int*) – Node id.
- **revision** (*int*) – First revision to get.

Returns Node status.

Return type dict

pauseBatch (*batch_id*)

Pause batch.

Parameters `batch_id (int)` – Batch id.

pauseNode (`node_id`)
Pause node.

Parameters `node_id (int)` – Node id.

quitNode (`node_id`)
Quit node.

Parameters `node_id (int)` – Node id.

resumeBatch (`batch_id`)
Resume batch.

Parameters `batch_id (int)` – Batch id.

resumeNode (`node_id`)
Resume node.

Parameters `node_id (int)` – Node id.

serverInfo ()
Get server information.

Returns Server information.

Return type dict

setBatchPriority (`batch_id, priority`)
Set batch priority.

Parameters

- **batch_id** (`int`) – Batch id.
- **priority** (`int`) – Batch priority (2 - Highest, 1 - High, 0 - Normal, -1 - Low, -2 - Lowest).

setNodeCapability (`node_id, capability`)
Set node capability.

Parameters

- **node_id** (`int`) – Node id.
- **capability** (`int`) – Node capability (1 - CPU, 2 - GPU, 3 - Any).

setNodePriority (`node_id, priority`)
Set node priority.

Parameters

- **node_id** (`int`) – Node id.
- **priority** (`int`) – Node priority (2 - Highest, 1 - High, 0 - Normal, -1 - Low, -2 - Lowest).

class PhotoScan.**NetworkTask**

NetworkTask class contains information about network task and its parameters.

The following example creates a new processing task and submits it to the server:

```
>>> import PhotoScan
>>> task = PhotoScan.NetworkTask()
>>> task.name = 'MatchPhotos'
>>> task.params['keypoint_limit'] = 40000
```



```

>>> client = PhotoScan.NetworkClient()
>>> client.connect('127.0.0.1')
>>> batch_id = client.createBatch('processing/project.psx', [task])
>>> client.resumeBatch(batch_id)

```

chunks

List of chunks.

Type list

frames

List of frames.

Type list

name

Task name.

Type string

params

Task parameters.

Type dict

class PhotoScan.**Orthomosaic**

Orthomosaic data.

The following sample assigns to the first shape in the chunk the image from the first camera for the orthomosaic patch and updates the mosaic:

```

>>> import PhotoScan
>>> chunk = PhotoScan.app.document.chunk
>>> ortho = chunk.orthomosaic
>>> camera = chunk.cameras[0]
>>> shape = chunk.shapes[0]
>>> patch = PhotoScan.Orthomosaic.Patch()
>>> patch.image_keys = [camera.key]
>>> ortho.patches[shape] = patch
>>> ortho.update()

```

class Patch

Orthomosaic patch.

copy()

Returns a copy of the patch.

Returns Copy of the patch.

Return type *Orthomosaic.Patch*

excluded

Excluded flag.

Type boolean

image_keys

Image keys.

Type list of int

class Orthomosaic.**Patches**

A set of orthomosaic patches.

items()

List of items.

keys()
List of item keys.

values()
List of item values.

Orthomosaic.bottom
Y coordinate of the bottom side.

Type float

Orthomosaic.crs
Coordinate system of orthomosaic.

Type *CoordinateSystem*

Orthomosaic.height
Orthomosaic height.

Type int

Orthomosaic.left
X coordinate of the left side.

Type float

Orthomosaic.meta
Orthomosaic meta data.

Type *MetaData*

Orthomosaic.patches
Orthomosaic patches.

Type *Orthomosaic.Patches*

Orthomosaic.removeOrthophotos()
Remove orthorectified images from orthomosaic.

Orthomosaic.reset([progress])
Reset all edits to orthomosaic.

Parameters **progress** (*Callable[[float], None]*) – Progress callback.

Orthomosaic.resolution
Orthomosaic resolution in meters.

Type float

Orthomosaic.right
X coordinate of the right side.

Type float

Orthomosaic.top
Y coordinate of the top side.

Type float

Orthomosaic.update([progress])
Apply edits to orthomosaic.

Parameters **progress** (*Callable[[float], None]*) – Progress callback.

Orthomosaic.width
Orthomosaic width.

Type int

class PhotoScan.**Photo**

Photo instance

alpha()

Returns alpha channel data.

Returns Alpha channel data.

Return type *Image*

copy()

Returns a copy of the photo.

Returns Copy of the photo.

Return type *Photo*

image()

Returns image data.

Returns Image data.

Return type *Image*

imageMeta()

Returns image meta data.

Returns Image meta data.

Return type *MetaData*

layer

Layer index in the image file.

Type int

meta

Frame meta data.

Type *MetaData*

open(*path*[, *layer*])

Loads specified image file.

Parameters

- **path** (*string*) – Path to the image file to be loaded.
- **layer** (*int*) – Optional layer index in case of multipage files.

path

Path to the image file.

Type string

thumbnail (*width=192, height=192*)

Creates new thumbnail with specified dimensions.

Returns Thumbnail data.

Return type *Thumbnail*

class PhotoScan.**PointClass**

Point class in [Created, Unclassified, Ground, LowVegetation, MediumVegetation, HighVegetation, Building,

LowPoint, ModelKeyPoint, Water, Rail, RoadSurface, OverlapPoints, WireGuard, WireConductor, TransmissionTower, WireConnector, BridgeDeck, HighNoise]

class PhotoScan.**PointCloud**

Sparse point cloud instance

class Cameras

Collection of *PointCloud.Projections* objects indexed by corresponding cameras

class PointCloud.**Filter**

Sparse point cloud filter

class Criterion

Point filternig criterion in [ReprojectionError, ReconstructionUncertainty, ImageCount, ProjectionAccuracy]

PointCloud.Filter.**init** (*points*, *criterion*, *progress*)

Initialize point cloud filter based on specified criterion.

Parameters

- **points** (*PointCloud* or *Chunk*) – Point cloud to filter.
- **criterion** (*PointCloud.Filter.Criterion*) – Point filter criterion.
- **progress** (*Callable[[float], None]*) – Progress callback.

PointCloud.Filter.**max_value**

Maximum value.

Type int or double

PointCloud.Filter.**min_value**

Minimum value.

Type int or double

PointCloud.Filter.**removePoints** (*threshold*)

Remove points based on specified threshold.

Parameters **threshold** (*float*) – Criterion threshold.

PointCloud.Filter.**resetSelection** ()

Reset previously made selection.

PointCloud.Filter.**selectPoints** (*threshold*)

Select points based on specified threshold.

Parameters **threshold** (*float*) – Criterion threshold.

PointCloud.Filter.**values**

List of values.

Type list of int or list of double

class PointCloud.**Point**

3D point in the point cloud

coord

Point coordinates.

Type *Vector*

selected

Point selection flag.

Type boolean

track_id

Track index.

Type int

valid
Point valid flag.
Type boolean

class `PointCloud.Points`
Collection of 3D points in the point cloud

class `PointCloud.Projection`
Projection of the 3D point on the photo

coord
Projection coordinates.
Type tuple of 2 float

size
Point size.
Type float

track_id
Track index.
Type int

class `PointCloud.Projections`
Collection of `PointCloud.Projection` for the camera

copy()
Returns a copy of projections buffer.
Returns Copy of projections buffer.
Return type `PointCloud.Projections`

class `PointCloud.Track`
Track in the point cloud

color
Track color.
Type tuple of 3 int

class `PointCloud.Tracks`
Collection of tracks in the point cloud

`PointCloud.copy()`
Returns a copy of the point cloud.
Returns Copy of the point cloud.
Return type `PointCloud`

`PointCloud.cropSelectedPoints()`
Crop selected points.

`PointCloud.cropSelectedTracks()`
Crop selected tie points.

`PointCloud.export(path, format='obj', projection)`
Export point cloud.

Parameters

- **path** (*string*) – Path to output file.
- **format** (*string*) – Export format in ['obj', 'ply'].
- **projection** (*Matrix* or *CoordinateSystem*) – Sets output projection.

`PointCloud.meta`

Point cloud meta data.

Type `MetaData`

`PointCloud.pickPoint (origin, target)`

Returns ray intersection with the point cloud (point on the ray nearest to some point).

Parameters

- **origin** (`PhotoScan.Vector`) – Ray origin.
- **target** (`PhotoScan.Vector`) – Point on the ray.

Returns Coordinates of the intersection point.

Return type `PhotoScan.Vector`

`PointCloud.points`

List of points.

Type `PointCloudPoints`

`PointCloud.projections`

Point projections for each photo.

Type `PointCloudProjections`

`PointCloud.removeSelectedPoints ()`

Remove selected points.

`PointCloud.removeSelectedTracks ()`

Remove selected tie points.

`PointCloud.tracks`

List of tracks.

Type `PointCloudTracks`

class `PhotoScan.PointsFormat`

Point cloud format in [PointsFormatOBJ, PointsFormatPLY, PointsFormatXYZ, PointsFormatLAS, PointsFormatExpe, PointsFormatU3D, PointsFormatPDF, PointsFormatE57, PointsFormatOC3, PointsFormatPotree, PointsFormatLAZ, PointsFormatCL3, PointsFormatPTS, PointsFormatDXF]

class `PhotoScan.Preselection`

Image pair preselection in [NoPreselection, GenericPreselection, ReferencePreselection]

class `PhotoScan.Quality`

Dense point cloud quality in [UltraQuality, HighQuality, MediumQuality, LowQuality, LowestQuality]

class `PhotoScan.RasterFormat`

Raster format in [RasterFormatTiles, RasterFormatKMZ, RasterFormatXYZ, RasterFormatMBTiles, RasterFormatWW]

class `PhotoScan.RasterTransform`

Raster transform definition.

calibrateRange ()

Auto detect range based on orthomosaic histogram.

enabled

Enable flag.

Type `boolean`

false_color
False color channels.

Type list

formula
Raster calculator expression.

Type string

interpolation
Interpolation enable flag.

Type boolean

palette
Color palette.

Type dict

range
Palette mapping range.

Type tuple

reset ()
Reset raster transform.

class PhotoScan.**RasterTransformType**
Raster transformation type in [RasterTransformNone, RasterTransformValue, RasterTransformPalette]

class PhotoScan.**ReferenceFormat**
Reference format in [ReferenceFormatXML, ReferenceFormatTEL, ReferenceFormatCSV, ReferenceFormatMavinci, ReferenceFormatBramor]

class PhotoScan.**ReferenceItems**
Reference items in [ReferenceItemsCameras, ReferenceItemsMarkers, ReferenceItemsScalebars]

class PhotoScan.**Region**
Region parameters

center
Region center coordinates.

Type *Vector*

rot
Region rotation matrix.

Type *Matrix*

size
Region size.

Type *Vector*

class PhotoScan.**RotationOrder**
Rotation order in [RotationOrderXYZ, RotationOrderXZY, RotationOrderYXZ, RotationOrderYZX, RotationOrderZXY, RotationOrderZYX]

class PhotoScan.**Scalebar**
Scale bar instance

class **Reference**
Scale bar reference data

accuracy
Scale bar length accuracy.
Type float

distance
Scale bar length.
Type float

enabled
Enabled flag.
Type boolean

`Scalebar.frames`
Scale bar frames.
Type list of *Scalebar*

`Scalebar.group`
Scale bar group.
Type *ScalebarGroup*

`Scalebar.key`
Scale bar identifier.
Type int

`Scalebar.label`
Scale bar label.
Type string

`Scalebar.meta`
Scale bar meta data.
Type *MetaData*

`Scalebar.point0`
Start of the scale bar.
Type *Marker*

`Scalebar.point1`
End of the scale bar.
Type *Marker*

`Scalebar.reference`
Scale bar reference data.
Type *ScalebarReference*

`Scalebar.selected`
Selects/deselects the scale bar.
Type boolean

class `PhotoScan.ScalebarGroup`
ScalebarGroup objects define groups of multiple scale bars. The grouping is established by assignment of a ScalebarGroup instance to the Scalebar.group attribute of participating scale bars.

label
Scale bar group label.
Type string

selected

Current selection state.

Type boolean

class PhotoScan.**Sensor**

Sensor instance

class **Type**

Sensor type in [Frame, Fisheye, Spherical]

Sensor.antenna

GPS antenna correction.

Type *Antenna*

Sensor.bands

List of image bands.

Type list of string

Sensor.calibration

Refined calibration of the photo.

Type *Calibration*

Sensor.fixed

Fix calibration flag.

Type boolean

Sensor.focal_length

Focal length in mm.

Type float

Sensor.height

Image height.

Type int

Sensor.key

Sensor identifier.

Type int

Sensor.label

Sensor label.

Type string

Sensor.pixel_height

Pixel height in mm.

Type float

Sensor.pixel_size

Pixel size in mm.

Type *Vector*

Sensor.pixel_width

Pixel width in mm.

Type float

Sensor.plane_count
Number of image planes.

Type int

Sensor.planes
Sensor planes.

Type list of *Sensor*

Sensor.type
Sensor projection model.

Type *Sensor.Type*

Sensor.user_calib
Custom calibration used as initial calibration during photo alignment.

Type *Calibration*

Sensor.width
Image width.

Type int

class PhotoScan.Shape
Shape data.

class BoundaryType
Shape boundary type in [NoBoundary, OuterBoundary, InnerBoundary]

class Shape.Type
Shape type in [Point, Polyline, Polygon]

class Shape.Vertices
Collection of shape vertices

Shape.area()
Return area of the shape on DEM.

Returns Shape area.

Return type float

Shape.attributes
Shape attributes.

Type *MetaData*

Shape.boundary_type
Shape boundary type.

Type *Shape.BoundaryType*

Shape.group
Shape group.

Type *ShapeGroup*

Shape.has_z
Z enable flag.

Type boolean

Shape.key
Shape identifier.

Type int

Shape.label
Shape label.

Type string

Shape.perimeter2D()
Return perimeter of the shape on DEM.

Returns Shape perimeter.

Return type float

Shape.perimeter3D()
Return perimeter of the shape.

Returns Shape perimeter.

Return type float

Shape.selected
Selects/deselects the shape.

Type boolean

Shape.type
Shape type.

Type *Shape.Type*

Shape.vertex_ids
List of shape vertex ids.

Type ShapeVertices

Shape.vertices
List of shape vertices.

Type ShapeVertices

Shape.volume (*level='bestfit'*)
Return volume of the shape measured on DEM above and below best fit, mean level or custom level plane.

Parameters **level** (*float*) – Plane level: 'bestfit', 'mean' or custom value.

Returns Shape volumes.

Return type dict

class PhotoScan.**ShapeGroup**

ShapeGroup objects define groups of multiple shapes. The grouping is established by assignment of a ShapeGroup instance to the Shape.group attribute of participating shapes.

color
Shape group color.

Type tuple of 3 int

enabled
Enable flag.

Type boolean

key
Shape group identifier.

Type int

label
Shape group label.

Type string

selected
Current selection state.

Type boolean

show_labels
Shape labels visibility flag.

Type boolean

class PhotoScan.**Shapes**
A set of shapes for a chunk frame.

addGroup()
Add new shape group to the set of shapes.

Returns Created shape group.

Return type *ShapeGroup*

addShape()
Add new shape to the set of shapes.

Returns Created shape.

Return type *Shape*

crs
Shapes coordinate system.

Type *CoordinateSystem*

groups
List of shape groups.

Type list of *ShapeGroup*

items()
List of items.

meta
Shapes meta data.

Type *MetaData*

remove(items)
Remove items from the shape layer.

Parameters **items** (list of *Shape* or *ShapeGroup*) – A list of items to be removed.

shapes
List of shapes.

Type list of *Shape*

class PhotoScan.**Shutter**
Shutter object contains estimated parameters of the rolling shutter correction model.

rotation
Rotation matrix of the rolling shutter model.

Type *Matrix*

translation

Translation vector of the rolling shutter model.

Type *Vector*

class `PhotoScan.SurfaceType`

Surface type in [Arbitrary, HeightField]

class `PhotoScan.TargetType`

Target type in [CircularTarget12bit, CircularTarget14bit, CircularTarget16bit, CircularTarget20bit, CircularTarget, CrossTarget]

class `PhotoScan.Thumbnail`

Thumbnail instance

copy ()

Returns a copy of thumbnail.

Returns Copy of thumbnail.

Return type *Thumbnail*

image ()

Returns image data.

Returns Image data.

Return type *Image*

load (*path* [, *layer*])

Loads thumbnail from file.

Parameters

- **path** (*string*) – Path to the image file to be loaded.
- **layer** (*int*) – Optional layer index in case of multipage files.

setImage (*image*)

Parameters **image** (*Image*) – Image object with thumbnail data.

class `PhotoScan.Thumbnails`

A set of thumbnails generated for a chunk frame.

items ()

List of items.

keys ()

List of item keys.

meta

Thumbnails meta data.

Type *MetaData*

values ()

List of item values.

class `PhotoScan.TiffCompression`

Tiff compression in [TiffCompressionNone, TiffCompressionLZW, TiffCompressionJPEG, TiffCompressionPackbits, TiffCompressionDeflate]

class `PhotoScan.TiledModel`

Tiled model data.

meta

Tiled model meta data.

Type `MetaData`

pickPoint (*origin, target*)

Returns ray intersection with the tiled model.

Parameters

- **origin** (`PhotoScan.Vector`) – Ray origin.
- **target** (`PhotoScan.Vector`) – Point on the ray.

Returns Coordinates of the intersection point.

Return type `PhotoScan.Vector`

class `PhotoScan.TiledModelFormat`

Tiled model format in [TiledModelFormatTLS, TiledModelFormatLOD, TiledModelFormatZIP]

class `PhotoScan.Utills`

Utility functions.

createDifferenceMask (*image, background, tolerance=10, fit_colors=True*)

Creates mask from a pair of images or an image and specified color.

Parameters

- **image** (`Image`) – Image to be masked.
- **background** (`Image` or color tuple) – Background image or color value.
- **tolerance** (`int`) – Tolerance value.
- **fit_colors** (`boolean`) – Enables white balance correction.

Returns Resulting mask.

Return type `Image`

createMarkers (*chunk, projections*)

Creates markers from a list of non coded projections.

Parameters

- **chunk** (`Chunk`) – Chunk to create markers in.
- **projections** (list of (`Camera`, x, y, r) tuples) – List of marker projections.

estimateImageQuality (*image*)

Estimates image sharpness.

Parameters **image** (`Image`) – Image to be analyzed.

Returns Quality metric.

Return type float

mat2opk (*R*)

Calculate omega, phi, kappa from camera to world rotation matrix.

Parameters **R** (`Matrix`) – Rotation matrix.

Returns Omega, phi, kappa angles in degrees.

Return type *Vector*

mat2ypr (*R*)

Calculate yaw, pitch, roll from camera to world rotation matrix.

Parameters *R* (*Matrix*) – Rotation matrix.

Returns Yaw, pitch roll angles in degrees.

Return type *Vector*

opk2mat (*angles*)

Calculate camera to world rotation matrix from omega, phi, kappa angles.

Parameters *angles* (*Vector*) – Omega, phi, kappa angles in degrees.

Returns Rotation matrix.

Return type *Matrix*

ypr2mat (*angles*)

Calculate camera to world rotation matrix from yaw, pitch, roll angles.

Parameters *angles* (*Vector*) – Yaw, pitch, roll angles in degrees.

Returns Rotation matrix.

Return type *Matrix*

class PhotoScan.**Vector**

n-component vector

```
>>> import PhotoScan
>>> vect = PhotoScan.Vector( (1, 2, 3) )
>>> vect2 = vect.copy()
>>> vect2.size = 4
>>> vect2.w = 5
>>> vect2 *= -1.5
>>> vect.size = 4
>>> vect.normalize()
>>> PhotoScan.app.messageBox("Scalar product is " + str(vect2 * vect))
```

copy ()

Return a copy of the vector.

Returns A copy of the vector.

Return type *Vector*

norm ()

Return norm of the vector.

norm2 ()

Return squared norm of the vector.

normalize ()

Normalize vector to the unit length.

normalized ()

Return a new, normalized vector.

Returns a normalized copy of the vector

Return type *Vector*

size
Vector dimensions.

Type int

w
Vector W component.

Type float

x
Vector X component.

Type float

y
Vector Y component.

Type float

z
Vector Z component.

Type float

zero ()
Set all elements to zero.

class PhotoScan.**Viewpoint** (*app*)
Represents viewpoint in the model view

center
Camera center.

Type *Vector*

coo
Center of orbit.

Type *Vector*

fov
Camera vertical field of view in degrees.

Type float

height
OpenGL window height.

Type int

mag
Camera magnification defined by distance to the center of rotation.

Type float

rot
Camera rotation matrix.

Type *Matrix*

width
OpenGL window width.

Type int

PYTHON API CHANGE LOG

3.1 PhotoScan version 1.3.2

- Added `vertex_colors` argument to `Chunk.buildModel()` method
- Added `Shape.vertex_ids` attribute

3.2 PhotoScan version 1.3.1

- Added `Settings` and `TiledModel` classes
- Added `Application.getBool()` method
- Added `Camera.unproject()` method
- Added `Chunk.addFrames()`, `Chunk.addMarkerGroup()`, `Chunk.addScalebarGroup()` and `Chunk.buildSeamlines()` methods
- Added `DenseCloud.pickPoint()` and `DenseCloud.updateStatistics()` methods
- Added `Elevation.altitude()` method
- Added `Matrix.svd()` method
- Added `Model.pickPoint()` method
- Added `Orthomosaic.reset()` and `Orthomosaic.update()` methods
- Added `PointCloud.pickPoint()` method
- Added `filter` argument to `Application.getOpenFileName()`, `Application.getOpenFileNames()` and `Application.getSaveFileName()` methods
- Added `point` and `visibility` arguments to `Chunk.addMarker()` method
- Added `raster_transform` and `write_scheme` arguments to `Chunk.exportDem()` method
- Added `write_scheme` and `white_background` arguments to `Chunk.exportOrthomosaic()` method
- Added `white_background` argument to `Chunk.exportOrthophotos()` method
- Added `projection` argument to `Chunk.exportMarkers()` method
- Added `markers` argument to `Chunk.exportModel()` method
- Added `pairs` argument to `Chunk.matchPhotos()` method
- Added `columns` and `delimiter` arguments to `Chunk.saveReference()` method

- Added version argument to Document.save() method
- Renamed npasses argument in Chunk.smoothModel() method to strength and changed its type to float
- Renamed from and to arguments in CoordinateSystem.transform(), DenseCloud.assignClass(), DenseCloud.assignClassToSelection() and DenseCloud.classifyGroundPoints() methods to avoid collision with reserved words
- Added Application.settings attribute
- Added Chunk.tiled_model attribute
- Added ShapeGroup.color and ShapeGroup.show_labels attributes
- Added ImageFormatTGA to ImageFormat enum

3.3 PhotoScan version 1.3.0

- Added MarkerGroup, Masks, ScalebarGroup, Shutter and Thumbnails classes
- Added Application.PhotosPane class
- Added Model.Statistics class
- Added Orthomosaic.Patch and Orthomosaic.Patches classes
- Added PointCloud.Filter class
- Added CamerasFormat, EulerAngles, ImageFormat, ImageLayout, MaskOperation, MaskSource, MatchesFormat, ModelFormat, ModelViewMode, PointClass, PointsFormat, RasterFormat, ReferenceFormat, ReferenceItems, RotationOrder, TiffCompression, TiledModelFormat enums
- Added Application.captureOrthoView() method
- Added Chunk.refineMarkers() method
- Added CoordinateSystem.listBuiltinCRS() class method
- Added Matrix.translation() method
- Added Model.statistics() method
- Added NetworkClient.serverInfo(), NetworkClient.nodeStatus(), NetworkClient.setNodeCapability() and NetworkClient.quitNode() methods
- Added Photo.imageMeta() method
- Added Shape.area(), Shape.perimeter2D(), Shape.perimeter3D() and Shape.volume() methods
- Added Utils.createMarkers() method
- Added source argument to Application.captureModelView() method
- Added image_format argument to Chunk.exportDem() method
- Added write_alpha argument to Chunk.exportOrthophotos() method
- Added image_format and write_alpha arguments to Chunk.exportOrthomosaic() method
- Added groups, projection, shift and progress arguments to Chunk.exportShapes() method
- Added items and progress arguments to Chunk.copy() method
- Added sensor argument to Chunk.addCamera() method
- Added layout argument to Chunk.addPhotos() method

- Added `jpeg_quality` argument to `Chunk.exportOrthomosaic()` and `Chunk.exportOrthophotos()` methods
- Added `fill_holes` argument to `Chunk.buildOrthomosaic()` method
- Added `fit_shutter` argument to `Chunk.optimizeCameras()` method
- Added `settings` argument to `Chunk.exportReport()` method
- Added `progress` argument to various `DenseCloud` methods
- Added `from` argument to `DenseCloud.classifyGroundPoints()` method
- Added `chunks` and `progress` arguments to `Document.append()` method
- Added `progress` argument to `Document.alignChunks()` and `Document.mergeChunks()` methods
- Added `revision` argument to `NetworkClient.batchList()`, `NetworkClient.batchStatus()` methods
- Added `Application.photos_pane` attribute
- Added `Camera.shutter` attribute
- Added `Chunk.masks` and `Chunk.thumbnails` attributes
- Added `Chunk.marker_groups` and `Chunk.scalebar_groups` attributes
- Added `Chunk.euler_angles` and `Chunk.scalebar_accuracy` attributes
- Added `CoordinateSystem.name` attribute
- Added `Marker.group` and `Scalebar.group` attributes
- Added `Orthomosaic.patches` attribute
- Added `RasterTransform.false_color` attribute
- Added `Sensor.bands` attribute
- Added `Shape.attributes` attribute
- Added `DepthMapsData`, `TiledModelData` and `OrthomosaicData` to `DataSource` enum
- Added `CircularTarget14bit` to `TargetType` enum
- Renamed `CameraReference` class to `Camera.Reference`
- Renamed `ConsolePane` class to `Application.ConsolePane`
- Renamed `MarkerProjection` class to `Marker.Projection`
- Renamed `MarkerProjections` class to `Marker.Projections`
- Renamed `MarkerReference` class `Marker.Reference`
- Renamed `MeshFace` class to `Model.Face`
- Renamed `MeshFaces` class to `Model.Faces`
- Renamed `MeshTexVertex` class to `Model.TexVertex`
- Renamed `MeshTexVertices` class to `Model.TexVertices`
- Renamed `MeshVertex` class to `Model.Vertex`
- Renamed `MeshVertices` class to `Model.Vertices`
- Renamed `PointCloudCameras` class to `PointCloud.Cameras`
- Renamed `PointCloudPoint` class to `PointCloud.Point`
- Renamed `PointCloudPoints` class to `PointCloud.Points`

- Renamed PointCloudProjection class to PointCloud.Projection
- Renamed PointCloudProjections class to PointCloud.Projections
- Renamed PointCloudTrack class to PointCloud.Track
- Renamed PointCloudTracks class to PointCloud.Tracks
- Renamed ScalebarReference class to Scalebar.Reference
- Renamed ShapeVertices class to Shape.Vertices
- Renamed Application.enumOpenCLDevices() method to Application.enumGPUDevices()
- Renamed Shape.boundary attribute to Shape.boundary_type
- Renamed Chunk.accuracy_cameras to Chunk.camera_location_accuracy
- Renamed Chunk.accuracy_cameras_ypr to Chunk.camera_rotation_accuracy
- Renamed Chunk.accuracy_markers to Chunk.marker_location_accuracy
- Renamed Chunk.accuracy_projections to Chunk.marker_projection_accuracy
- Renamed Chunk.accuracy_tiepoints to Chunk.tiepoint_accuracy
- Renamed method argument in Chunk.importMasks() method to source and changed its type to MaskSource
- Replaced preselection argument with generic_preselection and reference_preselection arguments in Chunk.matchPhotos() method
- Replaced fit_cxcy argument with fit_cx and fit_cy arguments in Chunk.optimizeCameras() method
- Replaced fit_k1k2k3 argument with fit_k1, fit_k2 and fit_k3 arguments in Chunk.optimizeCameras() method
- Replaced fit_p1p2 argument with fit_p1 and fit_p2 arguments in Chunk.optimizeCameras() method
- Replaced Application.cpu_cores_inactive with Application.cpu_enable attribute
- Changed type of source_data argument in Chunk.buildContours() to DataSource
- Changed type of format argument in Chunk.importCameras() and Chunk.exportCameras() methods to Cameras-Format
- Changed type of rotation_order argument in Chunk.exportCameras() to RotationOrder
- Changed type of format argument in Chunk.exportDem() and Chunk.exportOrthomosaic() methods to Raster-Format
- Changed type of format argument in Chunk.exportMatches() method to MatchesFormat
- Changed type of texture_format argument in Chunk.exportModel() method to ImageFormat
- Changed type of format argument in Chunk.importModel() and Chunk.exportModel() methods to ModelFormat
- Changed type of format argument in Chunk.exportPoints() method to PointsFormat
- Changed type of tiff_compression argument in Chunk.exportOrthomosaic() and Chunk.exportOrthophotos() methods to TiffCompression
- Changed type of items argument in Chunk.exportShapes() method to Shape.Type
- Changed type of format argument in Chunk.exportTiledModel() method to TiledModelFormat
- Changed type of mesh_format argument in Chunk.exportTiledModel() method to ModelFormat
- Changed type of operation argument in Chunk.importMasks() method to MaskOperation
- Changed type of format argument in Chunk.loadReference() and Chunk.saveReference() methods to Reference-Format

- Changed type of items argument in `Chunk.saveReference()` method to `ReferenceItems`
- Removed return values from `Camera.open()`, `Chunk.addPhotos()`, `Chunk.alignCameras()`, `Chunk.buildContours()`, `Chunk.buildDem()`, `Chunk.buildDenseCloud()`, `Chunk.buildModel()`, `Chunk.buildOrthomosaic()`, `Chunk.buildPoints()`, `Chunk.buildTexture()`, `Chunk.buildTiledModel()`, `Chunk.buildUV()`, `Chunk.decimateModel()`, `Chunk.detectMarkers()`, `Chunk.estimateImageQuality()`, `Chunk.exportCameras()`, `Chunk.exportDem()`, `Chunk.exportMarkers()`, `Chunk.exportMatches()`, `Chunk.exportModel()`, `Chunk.exportOrthomosaic()`, `Chunk.exportOrthophotos()`, `Chunk.exportPoints()`, `Chunk.exportReport()`, `Chunk.exportShapes()`, `Chunk.exportTiledModel()`, `Chunk.importCameras()`, `Chunk.importDem()`, `Chunk.importMarkers()`, `Chunk.importMasks()`, `Chunk.importModel()`, `Chunk.importShapes()`, `Chunk.loadReference()`, `Chunk.loadReferenceExif()`, `Chunk.matchPhotos()`, `Chunk.optimizeCameras()`, `Chunk.remove()`, `Chunk.saveReference()`, `Chunk.smoothModel()`, `Chunk.thinPointCloud()`, `Chunk.trackMarkers()`, `CirTransform.calibrate()`, `CoordinateSystem.init()`, `DenseCloud.classifyGroundPoints()`, `DenseCloud.compactPoints()`, `DenseCloud.selectMaskedPoints()`, `DenseCloud.selectPointsByColor()`, `Document.alignChunks()`, `Document.append()`, `Document.clear()`, `Document.mergeChunks()`, `Document.open()`, `Document.remove()`, `Document.save()`, `Mask.load()`, `Model.closeHoles()`, `Model.fixTopology()`, `Model.loadTexture()`, `Model.removeComponents()`, `Model.saveTexture()`, `Model.setTexture()`, `NetworkClient.abortBatch()`, `NetworkClient.abortNode()`, `NetworkClient.connect()`, `NetworkClient.pauseBatch()`, `NetworkClient.pauseNode()`, `NetworkClient.resumeBatch()`, `NetworkClient.resumeNode()`, `NetworkClient.setBatchPriority()`, `NetworkClient.setNodePriority()`, `Photo.open()`, `PointCloud.export()`, `RasterTransform.calibrateRange()`, `Thumbnail.load()` methods in favor of exceptions
- Removed `Chunk.exportContours()` method
- Removed obsolete `Matrix.diag()` and `Matrix.translation()` class methods
- Removed unused `focal_length` argument from `Calibration.save()` method
- Modified `Utils.mat2opk()` and `Utils.opk2mat()` methods to work with camera to world rotation matrices

3.4 PhotoScan version 1.2.6

No Python API changes

3.5 PhotoScan version 1.2.5

- Added `ShapeGroup` and `ShapeVertices` classes
- Added `CoordinateSystem.proj4` and `CoordinateSystem.geogcs` attributes
- Added `Shapes.shapes` and `Shapes.groups` attributes
- Added `Shape.label`, `Shape.vertices`, `Shape.group`, `Shape.has_z`, `Shape.key` and `Shape.selected` attributes
- Added `Shapes.addGroup()`, `Shapes.addShape()` and `Shapes.remove()` methods
- Added `CoordinateSystem.transform()` method
- Added `Matrix.Diag()`, `Matrix.Rotation()`, `Matrix.Translation()` and `Matrix.Scale()` class methods
- Added `Matrix.rotation()` and `Matrix.scale()` methods
- Added `DenseCloud.restorePoints()` and `DenseCloud.selectPointsByColor()` methods
- Added `Application.captureModelView()` method
- Added `Mask.invert()` method

- Added `adaptive_fitting` parameter to `Chunk.alignCameras()` method
- Added `load_rotation` and `load_accuracy` parameters to `Chunk.loadReferenceExif()` method
- Added `source` parameter to `Chunk.buildTiledModel()` method
- Added `fill_holes` parameter to `Chunk.buildTexture()` method

3.6 PhotoScan version 1.2.4

- Added `NetworkClient` and `NetworkTask` classes
- Added `Calibration.f`, `Calibration.b1`, `Calibration.b2` attributes
- Added `Chunk.exportMatches()` method
- Added `DenseCloud.compactPoints()` method
- Added `Orthomosaic.removeOrthophotos()` method
- Added `fit_b1` and `fit_b2` parameters to `Chunk.optimizeCameras()` method
- Added `tiff_big` parameter to `Chunk.exportOrthomosaic()`, `Chunk.exportDem()` and `Chunk.exportOrthophotos()` methods
- Added `classes` parameter to `Chunk.exportPoints()` method
- Added `progress` parameter to processing methods
- Removed `Calibration.fx`, `Calibration.fy`, `Calibration.skew` attributes

3.7 PhotoScan version 1.2.3

- Added `tiff_compression` parameter to `Chunk.exportOrthomosaic()` and `Chunk.exportOrthophotos()` methods

3.8 PhotoScan version 1.2.2

- Added `Camera.orientation` attribute
- Added `chunks` parameter to `Document.save()` method

3.9 PhotoScan version 1.2.1

- Added `CirTransform` and `RasterTransform` classes
- Added `Chunk.cir_transform` and `Chunk.raster_transform` attributes
- Added `Chunk.exportOrthophotos()` method
- Added `udim` parameter to `Chunk.exportModel()` method
- Renamed `RasterTransform` enum to `RasterTransformType`

3.10 PhotoScan version 1.2.0

- Added Elevation and Orthomosaic classes
- Added Shape and Shapes classes
- Added Antenna class
- Added DataSource enum
- Added Camera.error() method
- Added Chunk.buildContours() and Chunk.exportContours() methods
- Added Chunk.importShapes() and Chunk.exportShapes() methods
- Added Chunk.exportMarkers() and Chunk.importMarkers() methods
- Added Chunk.importDem() method
- Added Chunk.buildDem(), Chunk.buildOrthomosaic() and Chunk.buildTiledModel() methods
- Added PointCloud.removeSelectedPoints() and PointCloud.cropSelectedPoints() methods
- Added Utils.mat2opk(), Utils.mat2ypr(), Utils.opk2mat() and Utils.ypr2mat() methods
- Added Chunk.elevation, Chunk.orthomosaic and Chunk.shapes attributes
- Added Chunk.accuracy_cameras_ypr attribute
- Added Sensor.antenna, Sensor.plane_count and Sensor.planes attributes
- Added Calibration.p3 and Calibration.p4 attributes
- Added Camera.planes attribute
- Added CameraReference.accuracy_ypr attribute
- Added CameraReference.accuracy, MarkerReference.accuracy and ScalebarReference.accuracy attributes
- Added Application.activated attribute
- Added Chunk.image_brightness attribute
- Added fit_p3 and fit_p4 parameters to Chunk.optimizeCameras() method
- Added icon parameter to Application.addMenuItem() method
- Added title and description parameters to Chunk.exportReport() method
- Added operation parameter to Chunk.importMasks() method
- Added columns, delimiter, group_delimiters, skip_rows parameters to Chunk.loadReference() method
- Added items parameter to Chunk.saveReference() method
- Renamed Chunk.exportModelTiled() to Chunk.exportTiledModel()
- Renamed Chunk.exportOrthophoto() to Chunk.exportOrthomosaic()
- Removed OrthoSurface and PointsSource enums
- Removed PointCloud.groups attribute
- Removed Chunk.camera_offset attribute

3.11 PhotoScan version 1.1.1

- Added `Chunk.exportModelTiles()` method
- Added `noparity` parameter to `Chunk.detectMarkers()` method
- Added `blockw` and `blockh` parameters to `Chunk.exportPoints()` method

3.12 PhotoScan version 1.1.0

- Added `CameraOffset` and `ConsolePane` classes
- Added `CameraGroup`, `CameraReference`, `ChunkTransform`, `DepthMap`, `DepthMaps`, `MarkerReference`, `MarkerProjection`, `Mask`, `PointCloudGroups`, `PointCloudTrack`, `PointCloudTracks`, `ScalebarReference`, `Thumbnail` classes
- Added `Chunk.key`, `Sensor.key`, `Camera.key`, `Marker.key` and `Scalebar.key` attributes
- Added `Application.console` attribute
- Added `Application.addMenuSeparator()` method
- Added `Chunk.importMasks()` method
- Added `Chunk.addSensor()`, `Chunk.addCameraGroup()`, `Chunk.addCamera()`, `Chunk.addMarker()`, `Chunk.addScalebar()` methods
- Added `Chunk.addPhotos()`, `Chunk.addFrame()` methods
- Added `Chunk.master_channel` and `Chunk.camera_offset` attributes
- Added `Calibration.error()` method
- Added `Matrix.mulp()` and `Matrix.mulv()` methods
- Added `DenseCloud.assignClass()`, `DenseCloud.assignClassToSelection()`, `DenseCloud.removePoints()` methods
- Added `DenseCloud.classifyGroundPoints()` and `DenseCloud.selectMaskedPoints()` methods
- Added `Model.renderNormalMap()` method
- Added `DenseCloud.meta` and `Model.meta` attributes
- Added `PointCloud.tracks`, `PointCloud.groups` attributes
- Added `Image.tostring()` and `Image.fromstring()` methods
- Added `Image.channels` property
- Added U16 data type support in `Image` class
- Added `classes` parameter to `Chunk.buildModel()` method
- Added `crop_borders` parameter to `Chunk.exportDem()` method
- Added `chunk` parameter to `Document.addChunk()` method
- Added `format` parameter to `Calibration.save()` and `Calibration.load()` methods
- Moved OpenCL settings into `Application` class
- Converted string constants to enum objects

- Removed Cameras, Chunks, DenseClouds, Frame, Frames, GroundControl, GroundControlLocations, GroundControlLocation, Markers, MarkerPositions, Models, Scalebars, Sensors classes

3.13 PhotoScan version 1.0.0

- Added DenseCloud and DenseClouds classes
- Added Chunk.exportModel() and Chunk.importModel() methods
- Added Chunk.estimateImageQuality() method
- Added Chunk.buildDenseCloud() and Chunk.smoothModel() methods
- Added Photo.thumbnail() method
- Added Image.resize() method
- Added Application.enumOpenCLDevices() method
- Added Utils.estimateImageQuality() method
- Added Camera.meta, Marker.meta, Scalebar.meta and Photo.meta attributes
- Added Chunk.dense_cloud and Chunk.dense_clouds attributes
- Added page parameter to Model.setTexture() and Model.texture() methods
- Added shortcut parameter to Application.addMenuItem() method
- Added absolute_paths parameter to Document.save() method
- Added fit_f, fit_cxxy, fit_k1k2k3 and fit_k4 parameters to Chunk.optimizePhotos() method
- Changed parameters of Chunk.buildModel() and Chunk.buildTexture() methods
- Changed parameters of Chunk.exportPoints() method
- Changed parameters of Model.save() method
- Changed return value of Chunks.add() method
- Removed Chunk.buildDepth() method
- Removed Camera.depth() and Camera.setDepth() methods
- Removed Frame.depth() and Frame.setDepth() methods
- Removed Frame.depth_calib attribute

3.14 PhotoScan version 0.9.1

- Added Sensor, Scalebar and MetaData classes
- Added Camera.sensor attribute
- Added Chunk.sensors attribute
- Added Calibration.width, Calibration.height and Calibration.k4 attributes
- Added Chunk.refineMatches() method
- Added Model.area() and Model.volume() methods
- Added Model.renderDepth(), Model.renderImage() and Model.renderMask() methods

- Added `Chunk.meta` and `Document.meta` attributes
- Added `Calibration.project()` and `Calibration.unproject()` methods
- Added `Application.addMenuItem()` method
- Added `Model.closeHoles()` and `Model.fixTopology()` methods

3.15 PhotoScan version 0.9.0

- Added `Camera`, `Frame` and `CoordinateSystem` classes
- Added `Chunk.exportReport()` method
- Added `Chunk.trackMarkers()` and `Chunk.detectMarkers()` methods
- Added `Chunk.extractFrames()` and `Chunk.removeFrames()` methods
- Added `Chunk.matchPhotos()` method
- Added `Chunk.buildDepth()` and `Chunk.resetDepth()` methods
- Added `Chunk.cameras` property
- Added `Utils.createDifferenceMask()` method
- Revised `Chunk.alignPhotos()` method
- Revised `Chunk.buildPoints()` method
- Revised `Chunk.buildModel()` method
- Removed `Photo` class (deprecated)
- Removed `GeoProjection` class (deprecated)
- Removed `Chunk.photos` property (deprecated)

3.16 PhotoScan version 0.8.5

- Added `Chunk.fix_calibration` property
- Added `Chunk.exportCameras()` method
- Added `Chunk.exportPoints()` method for dense/sparse point cloud export
- Added `accuracy_cameras`, `accuracy_markers` and `accuracy_projections` properties to the `GroundControl` class
- Added `Image.undistort()` method
- Added `PointCloudPoint.selected` and `PointCloudPoint.valid` properties
- Added `GeoProjection.authority` property
- Added `GeoProjection.init()` method
- Moved `GroundControl.optimize()` method to `Chunk.optimize()`
- Removed “`fix_calibration`” parameter from `Chunk.alignPhotos()` method
- Removed `GeoProjection.epsg` property

3.17 PhotoScan version 0.8.4

- Added GroundControl.optimize() method
- Command line scripting support removed

3.18 PhotoScan version 0.8.3

Initial version of PhotoScan Python API

p

PhotoScan, 5